



XBinder

XML Schema Compiler
Version 2.5
C XML Runtime
Reference Manual

The software described in this document is furnished under a license agreement and may be used only in accordance with the terms of this agreement.

Copyright Notice

Copyright ©1997–2017 Objective Systems, Inc. All rights reserved.

This document may be distributed in any form, electronic or otherwise, provided that it is distributed in its entirety and that the copyright and this notice are included.

Author's Contact Information

Comments, suggestions, and inquiries regarding XBinder may be submitted via electronic mail to info@obj-sys.com.

Contents

1	Main Page	1
2	C DOM Runtime Library Functions	2
3	Module Index	4
3.1	Modules	4
4	Class Index	5
4.1	Class List	5
5	File Index	6
5.1	File List	6
6	Module Documentation	7
6.1	XML decode functions.	7
6.1.1	Function Documentation	9
6.1.1.1	rtXmlDecBase64Binary	9
6.1.1.2	rtXmlDecBase64Str	10
6.1.1.3	rtXmlDecBase64StrValue	10
6.1.1.4	rtXmlDecBigInt	11
6.1.1.5	rtXmlDecBool	11
6.1.1.6	rtXmlDecDate	11
6.1.1.7	rtXmlDecDateTime	12
6.1.1.8	rtXmlDecDecimal	12
6.1.1.9	rtXmlDecDouble	12
6.1.1.10	rtXmlDecDynBase64Str	13
6.1.1.11	rtXmlDecDynHexStr	13
6.1.1.12	rtXmlDecDynUTF8Str	13
6.1.1.13	rtXmlDecEmptyElement	14
6.1.1.14	rtXmlDecGDay	14

6.1.1.15	<code>rtXmlDecGMonth</code>	14
6.1.1.16	<code>rtXmlDecGMonthDay</code>	15
6.1.1.17	<code>rtXmlDecGYear</code>	15
6.1.1.18	<code>rtXmlDecGYearMonth</code>	15
6.1.1.19	<code>rtXmlDecHexBinary</code>	16
6.1.1.20	<code>rtXmlDecHexStr</code>	16
6.1.1.21	<code>rtXmlDecInt</code>	16
6.1.1.22	<code>rtXmlDecInt16</code>	17
6.1.1.23	<code>rtXmlDecInt64</code>	17
6.1.1.24	<code>rtXmlDecInt8</code>	17
6.1.1.25	<code>rtXmlDecNSAttr</code>	18
6.1.1.26	<code>rtXmlDecQName</code>	18
6.1.1.27	<code>rtXmlDecTime</code>	19
6.1.1.28	<code>rtXmlDecUInt</code>	19
6.1.1.29	<code>rtXmlDecUInt16</code>	19
6.1.1.30	<code>rtXmlDecUInt64</code>	20
6.1.1.31	<code>rtXmlDecUInt8</code>	20
6.1.1.32	<code>rtXmlDecUTF8Str</code>	20
6.1.1.33	<code>rtXmlDecXmlStr</code>	21
6.1.1.34	<code>rtXmlDecXSIAttr</code>	21
6.1.1.35	<code>rtXmlDecXSIArrs</code>	22
6.1.1.36	<code>rtXmlParseElementName</code>	22
6.1.1.37	<code>rtXmlParseElemQName</code>	22
6.2	<code>XML encode functions</code>	23
6.2.1	<code>Define Documentation</code>	29
6.2.1.1	<code>rtXmlGetEncBufLen</code>	29
6.2.1.2	<code>rtXmlGetEncBufPtr</code>	29
6.2.2	<code>Function Documentation</code>	30
6.2.2.1	<code>rtXmlEncAny</code>	30
6.2.2.2	<code>rtXmlEncAnyAttr</code>	30
6.2.2.3	<code>rtXmlEncAnyTypeValue</code>	30
6.2.2.4	<code>rtXmlEncBase64Binary</code>	31
6.2.2.5	<code>rtXmlEncBase64BinaryAttr</code>	31
6.2.2.6	<code>rtXmlEncBase64StrValue</code>	32
6.2.2.7	<code>rtXmlEncBigInt</code>	32
6.2.2.8	<code>rtXmlEncBigIntAttr</code>	32
6.2.2.9	<code>rtXmlEncBigIntValue</code>	33

6.2.2.10	rtXmlEncBinStrValue	33
6.2.2.11	rtXmlEncBitString	34
6.2.2.12	rtXmlEncBOM	34
6.2.2.13	rtXmlEncBool	34
6.2.2.14	rtXmlEncBoolAttr	35
6.2.2.15	rtXmlEncBoolValue	35
6.2.2.16	rtXmlEncComment	36
6.2.2.17	rtXmlEncDate	36
6.2.2.18	rtXmlEncDateTime	36
6.2.2.19	rtXmlEncDateTimeValue	37
6.2.2.20	rtXmlEncDateValue	37
6.2.2.21	rtXmlEncDecimal	37
6.2.2.22	rtXmlEncDecimalAttr	38
6.2.2.23	rtXmlEncDecimalValue	38
6.2.2.24	rtXmlEncDouble	39
6.2.2.25	rtXmlEncDoubleAttr	39
6.2.2.26	rtXmlEncDoubleNormalValue	39
6.2.2.27	rtXmlEncDoubleValue	40
6.2.2.28	rtXmlEncEmptyElement	40
6.2.2.29	rtXmlEncEndDocument	41
6.2.2.30	rtXmlEncEndElement	41
6.2.2.31	rtXmlEncEndSoapElems	41
6.2.2.32	rtXmlEncEndSoapEnv	42
6.2.2.33	rtXmlEncFloat	42
6.2.2.34	rtXmlEncFloatAttr	42
6.2.2.35	rtXmlEncGDay	43
6.2.2.36	rtXmlEncGDayValue	43
6.2.2.37	rtXmlEncGMonth	43
6.2.2.38	rtXmlEncGMonthDay	44
6.2.2.39	rtXmlEncGMonthDayValue	44
6.2.2.40	rtXmlEncGMonthValue	44
6.2.2.41	rtXmlEncGYear	45
6.2.2.42	rtXmlEncGYearMonth	45
6.2.2.43	rtXmlEncGYearMonthValue	45
6.2.2.44	rtXmlEncGYearValue	46
6.2.2.45	rtXmlEncHexBinary	46
6.2.2.46	rtXmlEncHexBinaryAttr	46

6.2.2.47	rtXmlEncHexStrValue	47
6.2.2.48	rtXmlEncIndent	47
6.2.2.49	rtXmlEncInt	47
6.2.2.50	rtXmlEncInt64	48
6.2.2.51	rtXmlEncInt64Attr	48
6.2.2.52	rtXmlEncInt64Value	49
6.2.2.53	rtXmlEncIntAttr	49
6.2.2.54	rtXmlEncIntPattern	49
6.2.2.55	rtXmlEncIntValue	50
6.2.2.56	rtXmlEncNamedBits	50
6.2.2.57	rtXmlEncNSAttrs	51
6.2.2.58	rtXmlEncReal10	51
6.2.2.59	rtXmlEncSoapArrayTypeAttr	51
6.2.2.60	rtXmlEncStartDocument	52
6.2.2.61	rtXmlEncStartElement	52
6.2.2.62	rtXmlEncStartSoapElems	53
6.2.2.63	rtXmlEncStartSoapEnv	53
6.2.2.64	rtXmlEncString	53
6.2.2.65	rtXmlEncStringValue	54
6.2.2.66	rtXmlEncStringValue2	54
6.2.2.67	rtXmlEncTermStartElement	54
6.2.2.68	rtXmlEncTime	55
6.2.2.69	rtXmlEncTimeValue	55
6.2.2.70	rtXmlEncUInt	55
6.2.2.71	rtXmlEncUInt64	56
6.2.2.72	rtXmlEncUInt64Attr	56
6.2.2.73	rtXmlEncUInt64Value	57
6.2.2.74	rtXmlEncUIntAttr	57
6.2.2.75	rtXmlEncUIntValue	57
6.2.2.76	rtXmlEncUnicodeStr	58
6.2.2.77	rtXmlEncUTF8Attr	58
6.2.2.78	rtXmlEncUTF8Attr2	58
6.2.2.79	rtXmlEncUTF8Str	59
6.2.2.80	rtXmlEncXSIAttrs	59
6.2.2.81	rtXmlEncXSINilAttr	60
6.2.2.82	rtXmlEncXSITypeAttr	60
6.2.2.83	rtXmlEncXSITypeAttr2	60

6.2.2.84	rtXmlFreeInputSource	61
6.2.2.85	rtXmlGetIndent	61
6.2.2.86	rtXmlGetIndentChar	61
6.2.2.87	rtXmlGetWriteBOM	61
6.2.2.88	rtXmlPrintNSAttrs	62
6.2.2.89	rtXmlSetEncBufPtr	62
6.3	XML utility functions	63
6.3.1	Function Documentation	63
6.3.1.1	rtXmlWriteToFile	63
6.4	XML pull-parser decode functions	64
6.4.1	Function Documentation	69
6.4.1.1	rtXmlEncAttrC14N	69
6.4.1.2	rtXmlpCountListItems	69
6.4.1.3	rtXmlpCreateReader	69
6.4.1.4	rtXmlpDecAny	70
6.4.1.5	rtXmlpDecAny2	70
6.4.1.6	rtXmlpDecAnyAttrStr	70
6.4.1.7	rtXmlpDecAnyElem	71
6.4.1.8	rtXmlpDecBase64Str	71
6.4.1.9	rtXmlpDecBigInt	72
6.4.1.10	rtXmlpDecBitString	72
6.4.1.11	rtXmlpDecBool	72
6.4.1.12	rtXmlpDecDate	73
6.4.1.13	rtXmlpDecDateTime	73
6.4.1.14	rtXmlpDecDecimal	73
6.4.1.15	rtXmlpDecDouble	74
6.4.1.16	rtXmlpDecDoubleExt	74
6.4.1.17	rtXmlpDecDynBase64Str	75
6.4.1.18	rtXmlpDecDynBitString	75
6.4.1.19	rtXmlpDecDynHexStr	75
6.4.1.20	rtXmlpDecDynUnicodeStr	76
6.4.1.21	rtXmlpDecDynUTF8Str	76
6.4.1.22	rtXmlpDecGDay	76
6.4.1.23	rtXmlpDecGMonth	77
6.4.1.24	rtXmlpDecGMonthDay	77
6.4.1.25	rtXmlpDecGYear	78
6.4.1.26	rtXmlpDecGYearMonth	78

6.4.1.27	rtXmlpDecHexStr	78
6.4.1.28	rtXmlpDecInt	79
6.4.1.29	rtXmlpDecInt16	79
6.4.1.30	rtXmlpDecInt64	79
6.4.1.31	rtXmlpDecInt8	80
6.4.1.32	rtXmlpDecNamedBits	80
6.4.1.33	rtXmlpDecStrList	81
6.4.1.34	rtXmlpDecTime	81
6.4.1.35	rtXmlpDecUInt	81
6.4.1.36	rtXmlpDecUInt16	82
6.4.1.37	rtXmlpDecUInt64	82
6.4.1.38	rtXmlpDecUInt8	82
6.4.1.39	rtXmlpDecUTF8Str	83
6.4.1.40	rtXmlpDecXmlStr	83
6.4.1.41	rtXmlpDecXmlStrList	83
6.4.1.42	rtXmlpDecXSIAtrr	84
6.4.1.43	rtXmlpDecXSIAtrrs	84
6.4.1.44	rtXmlpDecXSITypeAttr	84
6.4.1.45	rtXmlpForceDecodeAsGroup	85
6.4.1.46	rtXmlpGetAttributeCount	85
6.4.1.47	rtXmlpGetAttributeID	85
6.4.1.48	rtXmlpGetCurrentLevel	86
6.4.1.49	rtXmlpGetNextAllElemID	86
6.4.1.50	rtXmlpGetNextAllElemID16	86
6.4.1.51	rtXmlpGetNextAllElemID32	87
6.4.1.52	rtXmlpGetNextElem	87
6.4.1.53	rtXmlpGetNextElemID	88
6.4.1.54	rtXmlpGetNextSeqElemID	88
6.4.1.55	rtXmlpGetNextSeqElemID2	89
6.4.1.56	rtXmlpGetNextSeqElemIDExt	89
6.4.1.57	rtXmlpGetReader	90
6.4.1.58	rtXmlpGetXmlnsAttrs	90
6.4.1.59	rtXmlpGetXsITypeAttr	91
6.4.1.60	rtXmlpGetXsITypeIndex	91
6.4.1.61	rtXmlpHasAttributes	91
6.4.1.62	rtXmlpHideAttributes	92
6.4.1.63	rtXmlpIsDecodeAsGroup	92

6.4.1.64	<code>rtXmlpIsEmptyElement</code>	92
6.4.1.65	<code>rtXmlpIsLastEventDone</code>	92
6.4.1.66	<code>rtXmlpIsUTF8Encoding</code>	93
6.4.1.67	<code>rtXmlpListHasItem</code>	93
6.4.1.68	<code>rtXmlpLookupXSITypeIndex</code>	93
6.4.1.69	<code>rtXmlpMarkLastEventActive</code>	94
6.4.1.70	<code>rtXmlpMarkPos</code>	94
6.4.1.71	<code>rtXmlpMatchEndTag</code>	94
6.4.1.72	<code>rtXmlpMatchStartTag</code>	94
6.4.1.73	<code>rtXmlpNeedDecodeAttributes</code>	95
6.4.1.74	<code>rtXmlpReadBytes</code>	95
6.4.1.75	<code>rtXmlpResetMarkedPos</code>	95
6.4.1.76	<code>rtXmlpRewindToMarkedPos</code>	96
6.4.1.77	<code>rtXmlpSelectAttribute</code>	96
6.4.1.78	<code>rtXmlpSetListMode</code>	96
6.4.1.79	<code>rtXmlpSetMixedContentMode</code>	96
6.4.1.80	<code>rtXmlpSetNamespaceTable</code>	97
6.4.1.81	<code>rtXmlpSetWhiteSpaceMode</code>	97
6.5	XML run-time error status codes	98
6.5.1	Detailed Description	99
6.5.2	Define Documentation	99
6.5.2.1	<code>XML_E_BASE</code>	99
6.5.2.2	<code>XML_E_ELEMMISRQ</code>	100
6.5.2.3	<code>XML_E_ELEMSMISRQ</code>	100
6.5.2.4	<code>XML_E_FLDABSENT</code>	100
6.5.2.5	<code>XML_E_NOMATCH</code>	100
6.5.2.6	<code>XML_E_NSURINOTFOU</code>	100
6.5.2.7	<code>XML_E_TAGMISMATCH</code>	100
6.5.2.8	<code>XML_OK_EOB</code>	100
6.5.2.9	<code>XML_OK_FRAG</code>	101
6.6	DOM API functions	102
6.6.1	Function Documentation	103
6.6.1.1	<code>domAddAttribute</code>	103
6.6.1.2	<code>domAddCdata</code>	104
6.6.1.3	<code>domAddContent</code>	104
6.6.1.4	<code>domCreateChild</code>	104
6.6.1.5	<code>domCreateDocument</code>	105

6.6.1.6	domFreeDoc	105
6.6.1.7	domGetAttrData	105
6.6.1.8	domGetChild	106
6.6.1.9	domGetDoc	106
6.6.1.10	domGetElementName	106
6.6.1.11	domGetNext	106
6.6.1.12	domGetNextAttr	107
6.6.1.13	domGetNodeAttributesNum	107
6.6.1.14	domGetNodeContent	107
6.6.1.15	domGetNodeFirstAttribute	108
6.6.1.16	domGetRootElement	108
6.6.1.17	domParseFile	108
6.6.1.18	domSaveDoc	108
6.7	DOM runtime encode/decode functions.	110
6.7.1	Function Documentation	111
6.7.1.1	rtDomAddAttr	111
6.7.1.2	rtDomAddNode	111
6.7.1.3	rtDomAddNSAttrs	112
6.7.1.4	rtDomAddSubTree	112
6.7.1.5	rtDomDecodeDoc	112
6.7.1.6	rtDomEncAny	113
6.7.1.7	rtDomEncAnyAttr	113
6.7.1.8	rtDomEncString	114
6.7.1.9	rtDomEncStringValue	114
6.7.1.10	rtDomEncXSIAttrs	114
6.7.1.11	rtDomSetNode	115
7	Class Documentation	116
7.1	OSXMLGroupDesc Struct Reference	116
7.1.1	Detailed Description	116
8	File Documentation	117
8.1	osrtdom.h File Reference	117
8.1.1	Detailed Description	118
8.2	osrtxml.h File Reference	119
8.2.1	Detailed Description	136
8.2.2	Typedef Documentation	136
8.2.2.1	OSXMLGroupDesc	136

8.2.3	Function Documentation	136
8.2.3.1	<code>rtSaxGetAttrValue</code>	136
8.2.3.2	<code>rtSaxGetElemID</code>	137
8.2.3.3	<code>rtSaxGetElemID8</code>	137
8.2.3.4	<code>rtSaxHasXMLNSAttrs</code>	137
8.2.3.5	<code>rtSaxIsEmptyBuffer</code>	138
8.2.3.6	<code>rtSaxSortAttrs</code>	138
8.2.3.7	<code>rtSaxStrListMatch</code>	138
8.2.3.8	<code>rtSaxStrListParse</code>	138
8.2.3.9	<code>rtXmlCmpBase64Str</code>	139
8.2.3.10	<code>rtXmlCmpHexStr</code>	139
8.2.3.11	<code>rtXmlCreateFileInputSource</code>	139
8.2.3.12	<code>rtXmlInitContext</code>	140
8.2.3.13	<code>rtXmlInitContextUsingKey</code>	140
8.2.3.14	<code>rtXmlInitCtxtAppInfo</code>	140
8.2.3.15	<code>rtXmlMatchBase64Str</code>	140
8.2.3.16	<code>rtXmlMatchDate</code>	141
8.2.3.17	<code>rtXmlMatchDateTime</code>	141
8.2.3.18	<code>rtXmlMatchGDay</code>	141
8.2.3.19	<code>rtXmlMatchGMonth</code>	141
8.2.3.20	<code>rtXmlMatchGMonthDay</code>	142
8.2.3.21	<code>rtXmlMatchGYear</code>	142
8.2.3.22	<code>rtXmlMatchGYearMonth</code>	142
8.2.3.23	<code>rtXmlMatchHexStr</code>	142
8.2.3.24	<code>rtXmlMatchTime</code>	143
8.2.3.25	<code>rtXmlMemFreeAnyAttrs</code>	143
8.2.3.26	<code>rtXmlNewQName</code>	143
8.2.3.27	<code>rtXmlPrepareContext</code>	144
8.2.3.28	<code>rtXmlSetEncC14N</code>	144
8.2.3.29	<code>rtXmlSetEncDocHdr</code>	144
8.2.3.30	<code>rtXmlSetEncodingStr</code>	144
8.2.3.31	<code>rtXmlSetEncXSINamespace</code>	145
8.2.3.32	<code>rtXmlSetEncXSINilAttr</code>	145
8.2.3.33	<code>rtXmlSetFormatting</code>	145
8.2.3.34	<code>rtXmlSetIndent</code>	145
8.2.3.35	<code>rtXmlSetIndentChar</code>	146
8.2.3.36	<code>rtXmlSetNamespacesSet</code>	146

8.2.3.37	rtXmlSetNoNSSchemaLocation	146
8.2.3.38	rtXmlSetNSPrefixLinks	147
8.2.3.39	rtXmlSetSchemaLocation	147
8.2.3.40	rtXmlSetSoapVersion	147
8.2.3.41	rtXmlSetWriteBOM	147
8.2.3.42	rtXmlSetXSITypeAttr	148
8.3	rtXmlErrCodes.h File Reference	149
8.3.1	Detailed Description	150
8.4	rtXmlExternDefs.h File Reference	151
8.4.1	Detailed Description	151
8.5	rtXmlKeyArray.h File Reference	152
8.5.1	Detailed Description	152
8.5.2	Function Documentation	152
8.5.2.1	rtXmlKeyArrayAdd	152
8.5.2.2	rtXmlKeyArrayContains	153
8.5.2.3	rtXmlKeyArrayInit	153
8.5.2.4	rtXmlKeyArraySetDecimal	153
8.5.2.5	rtXmlKeyArraySetInt	153
8.5.2.6	rtXmlKeyArraySetString	153
8.5.2.7	rtXmlKeyArraySetUInt	153
8.6	rtXmlNamespace.h File Reference	154
8.6.1	Detailed Description	156
8.6.2	Define Documentation	156
8.6.2.1	RTXMLNSSETQNAME	156
8.6.3	Function Documentation	156
8.6.3.1	rtXmlNSAddNamespace	156
8.6.3.2	rtXmlNSEqual	157
8.6.3.3	rtXmlNSFreeAttrList	157
8.6.3.4	rtXmlNSGetAttrPrefix	157
8.6.3.5	rtXmlNSGetAttrQName	157
8.6.3.6	rtXmlNSGetPrefix	158
8.6.3.7	rtXmlNSGetPrefixCount	158
8.6.3.8	rtXmlNSGetPrefixIndex	158
8.6.3.9	rtXmlNSGetPrefixUsingIndex	159
8.6.3.10	rtXmlNSGetQName	159
8.6.3.11	rtXmlNSLookupPrefix	159
8.6.3.12	rtXmlNSLookupPrefixForURI	160

8.6.3.13	rtXmlNSLookupPrefixFrag	160
8.6.3.14	rtXmlNSLookupURI	160
8.6.3.15	rtXmlNSLookupURIInList	160
8.6.3.16	rtXmlNSNewPrefix	161
8.6.3.17	rtXmlNSRemoveAll	161
8.6.3.18	rtXmlNSSetNamespace	161
8.7	rtXmlpCppDecFuncs.h File Reference	162
8.7.1	Detailed Description	162

Chapter 1

Main Page

C XML Runtime Library Functions

The **C run-time XML library** contains functions used to encode/decode XML data. These functions are identified by their *rtXml* prefixes.

The categories of functions provided are as follows:

- XML pull-parser code.
- Functions functions to encode C types to XML.
- Functions to decode XML to C data types.
- Functions to encode XML element tags.
- Functions to encode XML attributes in sorted order for C14N.
- SAX parser interfaces.
- Context management functions.

Chapter 2

C DOM Runtime Library Functions

The **C run-time DOM library** contains functions used to encode/decode XML data in a DOM tree. These functions are identified by their *rtDom* prefixes.

The categories of functions provided are as follows:

- Functions to add nodes.
- Functions to add attributes to a node.
- Functions to add namespace and xsi:type information.
- Functions to encode data types to DOM.

Chapter 3

Module Index

3.1 Modules

Here is a list of all modules:

XML decode functions.	7
XML encode functions.	23
XML utility functions.	63
XML pull-parser decode functions.	64
XML run-time error status codes.	98
DOM API functions.	102
DOM runtime encode/decode functions.	110

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

OSXMLGroupDesc (OSXMLGroupDesc describes how entries in an OSXMLElemIDRec array make up a group)	116
---	-----

Chapter 5

File Index

5.1 File List

Here is a list of all documented files with brief descriptions:

domAPI.h	??
osrtdom.h (DOM low-level C encode/decode functions)	117
osrtxml.h (XML low-level C encode/decode functions)	119
rtLx2Dom.h	??
rtxDomDefs.h	??
rtXmlCtxtAppInfo.h	??
rtXmlEncDateTmpl.h	??
rtXmlErrCodes.h (List of numeric status codes that can be returned by ASN1C run-time functions and generated code)	149
rtXmlExternDefs.h (XML external definitions macro)	151
rtXmlKeyArray.h	(
• Implementation of a dynamic pointer sorted array	
)	152
rtXmlNamespace.h (XML namespace handling structures and function definitions)	154
rtXmlpCppDecFuncs.h (XML low-level C++ decode functions)	162
rtXmlPull.h	??

Chapter 6

Module Documentation

6.1 XML decode functions.

Functions

- int [rtXmlDecBase64Binary](#) (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, OSSIZE length)
This function decodes the contents of a Base64-encoded binary data type into a memory buffer.
- int [rtXmlDecBase64Str](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes a contents of a Base64-encode binary string into a static memory structure.
- int [rtXmlDecBase64StrValue](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSSIZE bufSize, OSSIZE srcDataLen)
This function decodes a contents of a Base64-encode binary string into the specified octet array.
- int [rtXmlDecBigInt](#) (OSCTXT *pctxt, const OSUTF8CHAR **ppvalue)
This function will decode a variable of the XSD integer type.
- int [rtXmlDecBool](#) (OSCTXT *pctxt, OSBOOL *pvalue)
This function decodes a variable of the boolean type.
- int [rtXmlDecDate](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'date' type.
- int [rtXmlDecTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'time' type.
- int [rtXmlDecDateTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'dateTime' type.
- int [rtXmlDecDecimal](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a decimal data type.
- int [rtXmlDecDouble](#) (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a float or double data type.

- int [rtXmlDecDynBase64Str](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a Base64-encode binary string.
- int [rtXmlDecDynHexStr](#) (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a hexBinary string.
- int [rtXmlDecEmptyElement](#) (OSCTXT *pctxt)
This function is used to enforce a requirement that an element be empty.
- int [rtXmlDecUTF8Str](#) (OSCTXT *pctxt, OSUTF8CHAR *outdata, OSSIZE max_len)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecDynUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR **outdata)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecHexBinary](#) (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, OSSIZE length)
This function decodes the contents of a hex-encoded binary data type into a memory buffer.
- int [rtXmlDecHexStr](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int [rtXmlDecGYear](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int [rtXmlDecGYearMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int [rtXmlDecGMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonth' type.
- int [rtXmlDecGMonthDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonthDay' type.
- int [rtXmlDecGDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gDay' type.
- int [rtXmlDecInt](#) (OSCTXT *pctxt, OSINT32 *pvalue)
This function decodes the contents of a 32-bit integer data type.
- int [rtXmlDecInt8](#) (OSCTXT *pctxt, OSINT8 *pvalue)
This function decodes the contents of an 8-bit integer data type (i.e.
- int [rtXmlDecInt16](#) (OSCTXT *pctxt, OSINT16 *pvalue)
This function decodes the contents of a 16-bit integer data type.
- int [rtXmlDecInt64](#) (OSCTXT *pctxt, OSINT64 *pvalue)
This function decodes the contents of a 64-bit integer data type.
- int [rtXmlDecUInt](#) (OSCTXT *pctxt, OSUINT32 *pvalue)
This function decodes the contents of an unsigned 32-bit integer data type.

- int **rtXmlDecUInt8** (OSCTXT *pctxt, OSUINT8 *pvalue)
This function decodes the contents of an unsigned 8-bit integer data type (i.e.
- int **rtXmlDecUInt16** (OSCTXT *pctxt, OSUINT16 *pvalue)
This function decodes the contents of an unsigned 16-bit integer data type.
- int **rtXmlDecUInt64** (OSCTXT *pctxt, OSUINT64 *pvalue)
This function decodes the contents of an unsigned 64-bit integer data type.
- int **rtXmlDecNSAttr** (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue, OSRTDList *pNSAttrs, const OSUTF8CHAR *nsTable[], OSUINT32 nsTableRowCount)
This function decodes an XML namespace attribute (xmlns).
- const OSUTF8CHAR * **rtXmlDecQName** (OSCTXT *pctxt, const OSUTF8CHAR *qname, const OSUTF8CHAR **prefix)
This function decodes an XML qualified name string (QName) type.
- int **rtXmlDecXSIAttr** (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue)
This function decodes XML schema instance (XSI) attribute.
- int **rtXmlDecXSIAttrs** (OSCTXT *pctxt, const OSUTF8CHAR *const *attrs, const char *typeName)
This function decodes XML schema instance (XSI) attributes.
- int **rtXmlDecXmlStr** (OSCTXT *pctxt, OSXMLSTRING *outdata)
This function decodes the contents of an XML string data type.
- int **rtXmlParseElementName** (OSCTXT *pctxt, OSUTF8CHAR **ppName)
This function parses the initial tag from an XML message.
- int **rtXmlParseElem QName** (OSCTXT *pctxt, OSXMLQName *pQName)
This function parses the initial tag from an XML message.

6.1.1 Function Documentation

6.1.1.1 int **rtXmlDecBase64Binary** (OSRTMEMBUF * *pMemBuf*, const OSUTF8CHAR * *inpdata*, OSSIZE *length*)

This function decodes the contents of a Base64-encoded binary data type into a memory buffer.

Input is expected to be a string of UTF-8 characters returned by an XML parser. The decoded data will be put into the memory buffer starting from the current position and bit offset. After all data is decoded the octet string may be fetched out.

This function is normally used in the 'characters' SAX handler.

Parameters

pMemBuf Memory buffer to which decoded binary data is to be appended.

inpdata Pointer to a source string to be decoded.

length Length of the source string (in characters).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.2 int rtXmlDecBase64Str (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSINT32 *bufsize*)

This function decodes a contents of a Base64-encode binary string into a static memory structure.

The octet string must be Base64 encoded. This function call is used to decode a sized base64Binary string production.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the bufsize input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.3 int rtXmlDecBase64StrValue (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSSIZE *bufSize*, OSSIZE *srcDataLen*)

This function decodes a contents of a Base64-encode binary string into the specified octet array.

The octet string must be Base64 encoded. This function call is used internally to decode both sized and non-sized base64binary string production.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the bufsize input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufSize A maximum size (in octets) of *pvalue* buffer. An error will occur if the number of octets in the decoded string is larger than this value.

srcDataLen An actual source data length (in octets) without whitespaces.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.4 int rtXmlDecBigInt (OSCTXT * *pctxt*, const OSUTF8CHAR ** *ppvalue*)

This function will decode a variable of the XSD integer type.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). For example, parameters used to calculate security values are typically larger than these sizes.

These variables are stored in character string constant variables. The radix should be 10. If it is necessary to convert to another radix, then use rtxBigIntSetStr or rtxBigIntToString functions.

Parameters

pctxt Pointer to context block structure.

ppvalue Pointer to a pointer to receive decoded UTF-8 string. Dynamic memory is allocated for the variable using the rtMemAlloc function. The decoded variable is represented as a string starting with appropriate prefix.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.5 int rtXmlDecBool (OSCTXT * *pctxt*, OSBOOL * *pvalue*)

This function decodes a variable of the boolean type.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.6 int rtXmlDecDate (OSCTXT * *pctxt*, OSXSDDateType * *pvalue*)

This function decodes a variable of the XSD 'date' type.

Input is expected to be a string of characters returned by an XML parser. The string should have CCYY-MM-DD format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateType type pointer points to a OSXSDDateType value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.7 int rtXmlDecDateTime (OSCTXT * *pctxt*, OSXSDDateTime * *pvalue*)

This function decodes a variable of the XSD 'dateTime' type.

Input is expected to be a string of characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.8 int rtXmlDecDecimal (OSCTXT * *pctxt*, OSREAL * *pvalue*)

This function decodes the contents of a decimal data type.

Input is expected to be a string of characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.9 int rtXmlDecDouble (OSCTXT * *pctxt*, OSREAL * *pvalue*)

This function decodes the contents of a float or double data type.

Input is expected to be a string of characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.10 int rtXmlDecDynBase64Str (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a contents of a Base64-encode binary string.

The octet string must be Base64 encoded. This function will allocate dynamic memory to store the decoded result.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated to hold the string using the rtxMemAlloc function.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.11 int rtXmlDecDynHexStr (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a contents of a hexBinary string.

This function will allocate dynamic memory to store the decoded result.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated to hold the string using the rtxMemAlloc function.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.12 int rtXmlDecDynUTF8Str (OSCTXT * *pctxt*, const OSUTF8CHAR ** *outdata*)

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of UTF-8 or Unicode characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

outdata Pointer to a pointer to receive decoded UTF-8 string. Memory is allocated for this string using the run-time memory manager.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.13 int rtXmlDecEmptyElement (OSCTXT * *pctxt*)

This function is used to enforce a requirement that an element be empty.

An error is returned in the current element has any element or character children. The last event must be the start tag.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.14 int rtXmlDecGDay (OSCTXT * *pctxt*, OSXSDDateType * *pvalue*)

This function decodes a variable of the XSD 'gDay' type.

Input is expected to be a string of characters returned by an XML parser. The string should have ---DD[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateType type pointer points to a OSXSDDateType value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.15 int rtXmlDecGMonth (OSCTXT * *pctxt*, OSXSDDateType * *pvalue*)

This function decodes a variable of the XSD 'gMonth' type.

Input is expected to be a string of characters returned by an XML parser. The string should have --MM[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateType type pointer points to a OSXSDDateType value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.16 int rtXmlDecGMonthDay (OSCTXT * *pctxt*, OSXSDDateTIme * *pvalue*)

This function decodes a variable of the XSD 'gMonthDay' type.

Input is expected to be a string of characters returned by an XML parser. The string should have --MM-DD[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateTIme type pointer points to a OSXSDDateTIme value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.17 int rtXmlDecGYear (OSCTXT * *pctxt*, OSXSDDateTIme * *pvalue*)

This function decodes a variable of the XSD 'gYear' type.

Input is expected to be a string of characters returned by an XML parser. The string should have CCYY[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateTIme type pointer points to a OSXSDDateTIme value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.18 int rtXmlDecGYearMonth (OSCTXT * *pctxt*, OSXSDDateTIme * *pvalue*)

This function decodes a variable of the XSD 'gYearMonth' type.

Input is expected to be a string of characters returned by an XML parser. The string should have CCYY-MM[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateTIme type pointer points to a OSXSDDateTIme value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.19 int rtXmlDecHexBinary (OSRTMEMBUF **pMemBuf*, const OSUTF8CHAR **inpdata*, OSSIZE *length*)

This function decodes the contents of a hex-encoded binary data type into a memory buffer.

Input is expected to be a string of UTF-8 characters returned by an XML parser. The decoded data will be put into the given memory buffer starting from the current position and bit offset. After all data is decoded the octet string may be fetched out.

This function is normally used in the 'characters' SAX handler.

Parameters

pMemBuf Pointer to memory buffer onto which the decoded binary data will be appended.

inpdata Pointer to a source string to be decoded.

length Length of the source string (in characters).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.20 int rtXmlDecHexStr (OSCTXT **pctxt*, OSOCTET **pvalue*, OSUINT32 **pnocts*, OSINT32 *bufsize*)

This function decodes the contents of a hexBinary string into a static memory structure.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the bufsize input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.21 int rtXmlDecInt (OSCTXT **pctxt*, OSINT32 **pvalue*)

This function decodes the contents of a 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 32-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.22 int rtXmlDecInt16 (OSCTXT **pctxt*, OSINT16 **pvalue*)

This function decodes the contents of a 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 16-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.23 int rtXmlDecInt64 (OSCTXT **pctxt*, OSINT64 **pvalue*)

This function decodes the contents of a 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.24 int rtXmlDecInt8 (OSCTXT **pctxt*, OSINT8 **pvalue*)

This function decodes the contents of an 8-bit integer data type (i.e.

a signed byte type in the range of -128 to 127). Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 8-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.25 int rtXmlDecNSAttr (OSCTXT * *pctxt*, const OSUTF8CHAR * *attrName*, const OSUTF8CHAR * *attrValue*, OSRTDList * *pNSAttrs*, const OSUTF8CHAR * *nsTable*[], OSUINT32 *nsTableRowCount*)

This function decodes an XML namespace attribute (xmlns).

It is assumed that the given attribute name is either 'xmlns' or 'xmlns:prefix'. The XML namespace prefix and URI are added to the given attribute list structure. The parsed namespace is also added to the namespace stack in the given context.

Parameters

pctxt Pointer to context structure.

attrName Name of the XML namespace attribute. This is assumed to contain either 'xmlns' (a default namespace declaration) or 'xmlns:prefix' where prefix is a namespace prefix.

attrValue XML namespace attribute value (a URI).

pNSAttrs List to receive parsed namespace values.

nsTable Namespace URI's parsed from schema.

nsTableRowCount Number of rows (URI's) in namespace table.

Returns

Zero if success or negative error code.

6.1.1.26 const OSUTF8CHAR* rtXmlDecQName (OSCTXT * *pctxt*, const OSUTF8CHAR * *qname*, const OSUTF8CHAR ** *prefix*)

This function decodes an XML qualified name string (QName) type.

This is a type that contains an optional namespace prefix followed by a colon and the local part of the name:

[NS 5] QName ::= (Prefix ':')? LocalPart

[NS 6] Prefix ::= NCName

[NS 7] LocalPart ::= NCName

Parameters

pctxt Pointer to context block structure.

qname String containing XML QName to be decoded.

prefix Pointer to string pointer to receive decoded prefix. This is optional. If NULL, the prefix will not be returned. If not-NULL, the prefix will be returned in memory allocated using *rtxMemAlloc* which must be freed using one of the *rtxMemFree* functions.

Returns

Pointer to local part of string. This is pointer to a location within the given string (i.e. a pointer to the character after the ':' or to the beginning of the string if it contains no colon). This pointer does not need to be freed.

6.1.1.27 int rtXmlDecTime (OSCTXT **pctxt*, OSXSDDateTime **pvalue*)

This function decodes a variable of the XSD 'time' type.

Input is expected to be a string of characters returned by an XML parser. The string should have one of following formats:

(1) hh-mm-ss.ss used if tz_flag = false (2) hh-mm-ss.ssZ used if tz_flag = false and tzo = 0 (3) hh-mm-ss.ss+HH:MM if tz_flag = false and tzo > 0 (4) hh-mm-ss.ss-HH:MM-MM:MM if tz_flag = false and tzo < 0

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateTime type pointer points to a OSXSDDateTime value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.28 int rtXmlDecUInt (OSCTXT **pctxt*, OSUINT32 **pvalue*)

This function decodes the contents of an unsigned 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 32-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.29 int rtXmlDecUInt16 (OSCTXT **pctxt*, OSUINT16 **pvalue*)

This function decodes the contents of an unsigned 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 16-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.30 int rtXmlDecUInt64 (OSCTXT **pctxt*, OSUINT64 **pvalue*)

This function decodes the contents of an unsigned 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 64-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.31 int rtXmlDecUInt8 (OSCTXT **pctxt*, OSUINT8 **pvalue*)

This function decodes the contents of an unsigned 8-bit integer data type (i.e.

a signed byte type in the range of 0 to 255). Input is expected to be a string of OSUTF8CHAR characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 8-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.32 int rtXmlDecUTF8Str (OSCTXT **pctxt*, OSUTF8CHAR **outdata*, OSSIZE *max_len*)

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of UTF-8 or Unicode characters returned by an XML parser.

Parameters

pctxt Pointer to context block structure.

- outdata*** Pointer to a block of memory to receive decoded UTF8 string.
max_len Size of memory block.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.33 int rtXmlDecXmlStr (OSCTXT **pctxt*, OSXMLSTRING **outdata*)

This function decodes the contents of an XML string data type.

This type contains a pointer to a UTF-8 character string plus flags that can be set to alter the encoding of the string (for example, the cdata flag allows the string to be encoded in a CDATA section). Input is expected to be a string of UTF-8 characters returned by an XML parser.

Parameters

- pctxt*** Pointer to context block structure.
outdata Pointer to an XML string structure to receive the decoded string. Memory is allocated for the string using the run-time memory manager.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.34 int rtXmlDecXSIAttr (OSCTXT **pctxt*, const OSUTF8CHAR **attrName*, const OSUTF8CHAR **attrValue*)

This function decodes XML schema instance (XSI) attribute.

These attributes include the XSI namespace declaration, the XSD schema location attribute, and the XSD no namespace schema location attribute.

Parameters

- pctxt*** Pointer to context block structure.
attrName Attribute's name to be decoded
attrValue Attribute's value to be decoded

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.35 int rtXmlDecXSIAttrs (OSCTXT * *pctxt*, const OSUTF8CHAR **const attrs*, const char * *typeName*)

This function decodes XML schema instance (XSI) attributes.

These attributes include the XSI namespace declaration, the XSD schema location attribute, and the XSD no namespace schema location attribute.

Parameters

- pctxt* Pointer to context block structure.
- attrs* Attributes-values array [attr, value]. Should be null-terminated.
- typeName* Name of parent type to add in error log, if would be necessary.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.36 int rtXmlParseElementName (OSCTXT * *pctxt*, OSUTF8CHAR ** *ppName*)

This function parses the initial tag from an XML message.

If the tag is a QName, only the local part of the name is returned.

Parameters

- pctxt* Pointer to OSCTXT structure
- ppName* Pointer to a pointer to receive decoded UTF-8 string. Dynamic memory is allocated for the variable using the rtxMemAlloc function.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.1.1.37 int rtXmlParseElemQName (OSCTXT * *pctxt*, OSXMLQName * *pQName*)

This function parses the initial tag from an XML message.

Parameters

- pctxt* Pointer to OSCTXT structure
- pQName* Pointer to a QName structure to receive parsed name prefix and local name. Dynamic memory is allocated for both name parts using the rtxMemAlloc function.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2 XML encode functions.

Defines

- #define `rtXmlGetEncBufPtr(pctxt)` (`pctxt->buffer.data`
This macro returns the start address of the encoded XML message.
- #define `rtXmlGetEncBufLen(pctxt)` (`pctxt->buffer.byteIndex`
This macro returns the length of the encoded XML message.

Functions

- int `rtXmlEncAny` (OSCTXT *pctxt, OSXMLSTRING *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD any type.
- int `rtXmlEncAnyTypeValue` (OSCTXT *pctxt, const OSUTF8CHAR *pvalue)
This function encodes a variable of the XSD anyType type.
- int `rtXmlEncAnyAttr` (OSCTXT *pctxt, OSRTDList *pAnyAttrList)
This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- int `rtXmlEncBase64Binary` (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD base64Binary type.
- int `rtXmlEncBase64BinaryAttr` (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)
This function encodes a variable of the XSD base64Binary type as an attribute.
- int `rtXmlEncBase64StrValue` (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value)
This function encodes a variable of the XSD base64Binary type.
- int `rtXmlEncBigInt` (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int `rtXmlEncBigIntAttr` (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *attrName, OSIZE attrNameLen)
This function encodes an XSD integer attribute value.
- int `rtXmlEncBigIntValue` (OSCTXT *pctxt, const OSUTF8CHAR *value)
This function encodes an XSD integer attribute value.
- int `rtXmlEncBitString` (OSCTXT *pctxt, OSUINT32 nbits, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the ASN.1 BIT STRING type.
- int `rtXmlEncBinStrValue` (OSCTXT *pctxt, OSUINT32 nbits, const OSOCTET *data)

This function encodes a binary string value as a sequence of '1's and '0's.

- int **rtXmlEncBool** (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD boolean type.

- int **rtXmlEncBoolValue** (OSCTXT *pctxt, OSBOOL value)

This function encodes a variable of the XSD boolean type.

- int **rtXmlEncBoolAttr** (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes an XSD boolean attribute value.

- int **rtXmlEncComment** (OSCTXT *pctxt, const OSUTF8CHAR *comment)

This function encodes an XML comment.

- int **rtXmlEncDate** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD 'date' type as a string.

- int **rtXmlEncDateValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a variable of the XSD 'date' type as a string.

- int **rtXmlEncTime** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD 'time' type as a string.

- int **rtXmlEncTimeValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a variable of the XSD 'time' type as a string.

- int **rtXmlEncDateTime** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric date/time value into an XML string representation.

- int **rtXmlEncDateTimeValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric date/time value into an XML string representation.

- int **rtXmlEncDecimal** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDecimalFmt *pFmtSpec)

This function encodes a variable of the XSD decimal type.

- int **rtXmlEncDecimalAttr** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen, const OSDecimalFmt *pFmtSpec)

This function encodes a variable of the XSD decimal type as an attribute.

- int **rtXmlEncDecimalValue** (OSCTXT *pctxt, OSREAL value, const OSDecimalFmt *pFmtSpec, char *pDestBuf, OSSIZE destBufSize)

This function encodes a value of the XSD decimal type.

- int **rtXmlEncDouble** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD double type.

- int **rtXmlEncDoubleAttr** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD double type as an attribute.

- int **rtXmlEncDoubleNormalValue** (OSCTXT *pctxt, OSREAL value, const OSDoubleFmt *pFmtSpec, int defaultPrecision)

This function encodes a normal (not +/-INF or NaN) value of the XSD double or float type.

- int **rtXmlEncDoubleValue** (OSCTXT *pctxt, OSREAL value, const OSDoubleFmt *pFmtSpec, int defaultPrecision)

This function encodes a value of the XSD double or float type.

- int **rtXmlEncEmptyElement** (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)

This function encodes an empty element tag value (<elemName/>).

- int **rtXmlEncEndDocument** (OSCTXT *pctxt)

This function adds trailer information and a null terminator at the end of the XML document being encoded.

- int **rtXmlEncEndElement** (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes an end element tag value (</elemName>).

- int **rtXmlEncEndSoapEnv** (OSCTXT *pctxt)

This function encodes a SOAP envelope end element tag (<SOAP-ENV:Envelope/>).

- int **rtXmlEncEndSoapElems** (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)

This function encodes SOAP end element tags.

- int **rtXmlEncFloat** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD float type.

- int **rtXmlEncFloatAttr** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD float type as an attribute.

- int **rtXmlEncGYear** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gYear element into an XML string representation.

- int **rtXmlEncGYearMonth** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gYearMonth element into an XML string representation.

- int **rtXmlEncGMonth** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gMonth element into an XML string representation.

- int **rtXmlEncGMonthDay** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gMonthDay element into an XML string representation.
- int **rtXmlEncGDay** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gDay element into an XML string representation.
- int **rtXmlEncGYearValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gYear value into an XML string representation.
- int **rtXmlEncGYearMonthValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gYearMonth value into an XML string representation.
- int **rtXmlEncGMonthValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gMonth value into an XML string representation.
- int **rtXmlEncGMonthDayValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gMonthDay value into an XML string representation.
- int **rtXmlEncGDayValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gDay value into an XML string representation.
- int **rtXmlEncHexBinary** (OSCTXT *pctxt, OSSIZE nocts, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD hexBinary type.
- int **rtXmlEncHexBinaryAttr** (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD hexBinary type as an attribute.
- int **rtXmlEncHexStrValue** (OSCTXT *pctxt, OSSIZE nocts, const OSOCTET *data)

This function encodes a variable of the XSD hexBinary type.
- int **rtXmlEncIndent** (OSCTXT *pctxt)

This function adds indentation whitespace to the output stream.
- int **rtXmlEncInt** (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD integer type.
- int **rtXmlEncIntValue** (OSCTXT *pctxt, OSINT32 value)

This function encodes a variable of the XSD integer type.
- int **rtXmlEncIntAttr** (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD integer type as an attribute (name="value").
- int **rtXmlEncIntPattern** (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSUTF8CHAR *pattern)

This function encodes a variable of the XSD integer type using a pattern to specify the format of the integer value.

- int **rtXmlEncInt64** (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD integer type.
- int **rtXmlEncInt64Value** (OSCTXT *pctxt, OSINT64 value)

This function encodes a variable of the XSD integer type.
- int **rtXmlEncInt64Attr** (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD integer type as an attribute (name="value").
- int **rtXmlEncNamedBits** (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSUINT32 nbits, const OSOCTET *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the ASN.1 BIT STRING type.
- int **rtXmlEncNSAttrs** (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function encodes namespace declaration attributes at the beginning of an XML document.
- int **rtXmlPrintNSAttrs** (const char *name, const OSRTDList *data)

This function prints a list of namespace attributes.
- int **rtXmlEncReal10** (OSCTXT *pctxt, const OSUTF8CHAR *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the ASN.1 REAL base 10 type.
- int **rtXmlEncSoapArrayTypeAttr** (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value, OSSIZE itemCount)

This function encodes the special SOAP encoding attrType attribute which specifies the number and type of elements in a SOAP array.
- int **rtXmlEncStartDocument** (OSCTXT *pctxt)

This function encodes the XML header text at the beginning of an XML document.
- int **rtXmlEncBOM** (OSCTXT *pctxt)

This function encodes the Unicode byte order mark header at the start of the document.
- int **rtXmlEncStartElement** (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)

This function encodes a start element tag value (<elemName>).
- int **rtXmlEncStartSoapEnv** (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function encodes a SOAP envelope start element tag.
- int **rtXmlEncStartSoapElems** (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)

This function encodes a SOAP envelope start element tag and an optional SOAP body or fault tag.
- int **rtXmlEncString** (OSCTXT *pctxt, OSXMLSTRING *pxmlstr, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD string type.

- int [rtXmlEncStringValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)
This function encodes a variable of the XSD string type.
- int [rtXmlEncStringValue2](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, OSSIZE valueLen)
This function encodes a variable of the XSD string type.
- int [rtXmlEncTermStartElement](#) (OSCTXT *pctxt)
This function terminates a currently open XML start element by adding either a '>' or '/>' (if empty) terminator.
- int [rtXmlEncUnicodeStr](#) (OSCTXT *pctxt, const OSUNICHAR *value, OSSIZE nchars, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a Unicode string value.
- int [rtXmlEncUTF8Attr](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value)
This function encodes an attribute in which the name and value are given as a null-terminated UTF-8 strings.
- int [rtXmlEncUTF8Attr2](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, OSSIZE nameLen, const OSUTF8CHAR *value, OSSIZE valueLen)
This function encodes an attribute in which the name and value are given as a UTF-8 strings with lengths.
- int [rtXmlEncUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a UTF-8 string value.
- int [rtXmlEncUInt](#) (OSCTXT *pctxt, OSUINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD unsigned integer type.
- int [rtXmlEncUIntValue](#) (OSCTXT *pctxt, OSUINT32 value)
This function encodes a variable of the XSD unsigned integer type.
- int [rtXmlEncUIntAttr](#) (OSCTXT *pctxt, OSUINT32 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)
This function encodes a variable of the XSD unsigned integer type as an attribute (name="value").
- int [rtXmlEncUInt64](#) (OSCTXT *pctxt, OSUINT64 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int [rtXmlEncUInt64Value](#) (OSCTXT *pctxt, OSUINT64 value)
This function encodes a variable of the XSD integer type.
- int [rtXmlEncUInt64Attr](#) (OSCTXT *pctxt, OSUINT64 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)
This function encodes a variable of the XSD integer type as an attribute (name="value").
- int [rtXmlEncXSIAttrs](#) (OSCTXT *pctxt, OSBOOL needXSI)
This function encodes XML schema instance (XSI) attributes at the beginning of an XML document.
- int [rtXmlEncXSITypeAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)
This function encodes an XML schema instance (XSI) type attribute value (xsi:type="value").

- int [rtXmlEncXSITypeAttr2](#) (OSCTXT *pctxt, const OSUTF8CHAR *typeNsUri, const OSUTF8CHAR *typeName)

This function encodes an XML schema instance (XSI) type attribute value (xsi:type="pfx:value").
- int [rtXmlEncXSINilAttr](#) (OSCTXT *pctxt)

This function encodes an XML nil attribute (xsi:nil="true").
- int [rtXmlFreeInputSource](#) (OSCTXT *pctxt)

This function closes an input source that was previously created with one of the create input source functions such as 'rtXmlCreateFileInputSource'.
- int [rtXmlSetEncBufPtr](#) (OSCTXT *pctxt, OSOCTET *bufaddr, OSSIZE bufsiz)

This function is used to set the internal buffer within the run-time library encoding context.
- int [rtXmlGetIndent](#) (OSCTXT *pctxt)

This function returns current XML output indent value.
- OSBOOL [rtXmlGetWriteBOM](#) (OSCTXT *pctxt)

This function returns whether the Unicode byte order mark will be encoded.
- int [rtXmlGetIndentChar](#) (OSCTXT *pctxt)

This function returns current XML output indent character value (default is space).

6.2.1 Define Documentation

6.2.1.1 #define rtXmlGetEncBufLen(pctxt) (pctxt)->buffer.byteIndex

This macro returns the length of the encoded XML message.

Parameters

pctxt Pointer to a context structure.

Definition at line 2495 of file osrtxml.h.

6.2.1.2 #define rtXmlGetEncBufPtr(pctxt) (pctxt)->buffer.data

This macro returns the start address of the encoded XML message.

If a static buffer was used, this is simply the start address of the buffer. If dynamic encoding was done, this will return the start address of the dynamic buffer allocated by the encoder.

Parameters

pctxt Pointer to a context structure.

Definition at line 2488 of file osrtxml.h.

6.2.2 Function Documentation

6.2.2.1 int rtXmlEncAny (OSCTXT **pctxt*, OSXMLSTRING **pvalue*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*)

This function encodes a variable of the XSD any type.

This is considered to be a fully-wrapped element of any type (for example: <myType>myData</myType>)

Parameters

pctxt Pointer to context block structure.

pvalue Value to be encoded. This is a string containing the fully-encoded XML text to be copied to the output stream.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.2 int rtXmlEncAnyAttr (OSCTXT **pctxt*, OSRTDList **pAnyAttrList*)

This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.

Parameters

pctxt Pointer to context block structure.

pAnyAttrList List of attributes.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.3 int rtXmlEncAnyTypeValue (OSCTXT **pctxt*, const OSUTF8CHAR **pvalue*)

This function encodes a variable of the XSD anyType type.

This is considered to be a fully-wrapped element of any type, possibly containing attributes. (for example: * <myType>myData</myType>)

Parameters

pctxt Pointer to context block structure.

pvalue Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.4 int rtXmlEncBase64Binary (OSCTXT * *pctxt*, OSUINT32 *nocts*, const OSOCTET * *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD base64Binary type.

Parameters

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.5 int rtXmlEncBase64BinaryAttr (OSCTXT * *pctxt*, OSUINT32 *nocts*, const OSOCTET * *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*)

This function encodes a variable of the XSD base64Binary type as an attribute.

Parameters

pctxt Pointer to context block structure.

nocts Number of octets in the value string.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length in bytes of the attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.6 int rtXmlEncBase64StrValue (OSCTXT **pctxt*, OSUINT32 *nocts*, const OSOCTET **value*)

This function encodes a variable of the XSD base64Binary type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

- pctxt*** Pointer to context block structure.
- nocts*** Number of octets in the value string.
- value*** Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.7 int rtXmlEncBigInt (OSCTXT **pctxt*, const OSUTF8CHAR **value*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*)

This function encodes a variable of the XSD integer type.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). For example, parameters used to calculate security values are typically larger than these sizes.

Items of this type are stored in character string constant variables. They can be represented as decimal strings (with no prefixes), as hexadecimal strings starting with a "0x" prefix, as octal strings starting with a "0o" prefix or as binary strings starting with a "0b" prefix. Other radices are currently not supported.

Parameters

- pctxt*** Pointer to context block structure.
- value*** A pointer to a character string containing the value to be encoded.
- elemName*** XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS*** Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.8 int rtXmlEncBigIntAttr (OSCTXT **pctxt*, const OSUTF8CHAR **value*, const OSUTF8CHAR **attrName*, OSSIZE *attrNameLen*)

This function encodes an XSD integer attribute value.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits).

Parameters

- pctxt*** Pointer to context block structure.

- value*** A pointer to a character string containing the value to be encoded.
- attrName*** XML attribute name. A name must be provided.
- attrNameLen*** Length in bytes of the attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.9 int rtXmlEncBigIntValue (OSCTXT * *pctxt*, const OSUTF8CHAR * *value*)

This function encodes an XSD integer attribute value.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). This function just puts the encoded value in the destination buffer or stream without any tags.

Parameters

- pctxt*** Pointer to context block structure.
- value*** A pointer to a character string containing the value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.10 int rtXmlEncBinStrValue (OSCTXT * *pctxt*, OSUINT32 *nbits*, const OSOCTET * *data*)

This function encodes a binary string value as a sequence of '1's and '0's.

Parameters

- pctxt*** Pointer to context block structure.
- nbits*** Number of bits in the value string.
- data*** Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.11 int rtXmlEncBitString (OSCTXT * *pctxt*, OSUINT32 *nbits*, const OSOCTET * *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the ASN.1 BIT STRING type.

The encoded data is a sequence of '1's and '0's. This is only used if named bits are not specified in the string (

See also

[rtXmlEncNamedBits](#)).

Parameters

pctxt Pointer to context block structure.

nbits Number of bits in the bit string.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.12 int rtXmlEncBOM (OSCTXT * *pctxt*)

This function encodes the Unicode byte order mark header at the start of the document.

It is called by *rtXmlEncStartDocument* and does not need to be called manually.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.13 int rtXmlEncBool (OSCTXT * *pctxt*, OSBOOL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD boolean type.

Parameters

pctxt Pointer to context block structure.

value Boolean value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.14 int rtXmlEncBoolAttr (OSCTXT * *pctxt*, OSBOOL *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*)

This function encodes an XSD boolean attribute value.

Parameters

pctxt Pointer to context block structure.

value Boolean value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length in bytes of the attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.15 int rtXmlEncBoolValue (OSCTXT * *pctxt*, OSBOOL *value*)

This function encodes a variable of the XSD boolean type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

pctxt Pointer to context block structure.

value Boolean value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.16 int rtXmlEncComment (OSCTXT * *pctxt*, const OSUTF8CHAR * *comment*)

This function encodes an XML comment.

The given text will be inserted in between XML comment start and end elements () .

Parameters

- pctxt* Pointer to context block structure.
- comment* The comment text.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.17 int rtXmlEncDate (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD 'date' type as a string.

This version of the function is used to encode an OSXSDDateTime value into CCYY-MM-DD format.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* OSXSDDateTime type pointer points to a OSXSDDateTime value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.18 int rtXmlEncDateTime (OSCTXT * *pctxt*, const OSXSDDateTime * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric date/time value into an XML string representation.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.19 int rtXmlEncDateTimeValue (OSCTXT * *pctxt*, const OSXSDDate * *pvalue*)

This function encodes a numeric date/time value into an XML string representation.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

- pctxt* Pointer to context block structure.
pvalue Pointer to value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.20 int rtXmlEncDateValue (OSCTXT * *pctxt*, const OSXSDDate * *pvalue*)

This function encodes a variable of the XSD 'date' type as a string.

This version of the function is used to encode an OSXSDDate value into CCYY-MM-DD format. This function just puts the encoded value in the destination buffer or stream without any tags.

Parameters

- pctxt* Pointer to context block structure.
pvalue OSXSDDate type pointer points to a OSXSDDate value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.21 int rtXmlEncDecimal (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, const OSDecimalFmt * *pFmtSpec*)

This function encodes a variable of the XSD decimal type.

Parameters

- pctxt* Pointer to context block structure.
value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

pFmtSpec Pointer to format specification structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.22 int rtXmlEncDecimalAttr (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*, const OSDecimalFmt * *pFmtSpec*)

This function encodes a variable of the XSD decimal type as an attribute.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length of XML attribute name.

pFmtSpec Pointer to format specification structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.23 int rtXmlEncDecimalValue (OSCTXT * *pctxt*, OSREAL *value*, const OSDecimalFmt * *pFmtSpec*, char * *pDestBuf*, OSSIZE *destBufSize*)

This function encodes a value of the XSD decimal type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

pFmtSpec Pointer to format specification structure.

pDestBuf Pointer to a destination buffer. If NULL (destBufSize should be 0) the encoded value will be put in pctxt->buffer or in stream associated with the pctxt.

destBufSize The size of the destination buffer. Must be 0, if pDestBuf is NULL.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.24 int rtXmlEncDouble (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD double type.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

pFmtSpec Pointer to format specification structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.25 int rtXmlEncDoubleAttr (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD double type as an attribute.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length of XML attribute name.

pFmtSpec Pointer to format specification structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.26 int rtXmlEncDoubleNormalValue (OSCTXT * *pctxt*, OSREAL *value*, const OSDoubleFmt * *pFmtSpec*, int *defaultPrecision*)

This function encodes a normal (not +/-INF or NaN) value of the XSD double or float type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

pFmtSpec Pointer to format specification structure.

defaultPrecision Default precision of the value. For float, it is 6, for double it is 15.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.27 int rtXmlEncDoubleValue (OSCTXT * *pctxt*, OSREAL *value*, const OSDoubleFmt * *pFmtSpec*, int *defaultPrecision*)

This function encodes a value of the XSD double or float type.

It just puts the encoded value in the destination buffer or stream without any tags. Special real values +/-INF and NaN are encoded as "INF", "-INF", and "NaN", respectively.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

pFmtSpec Pointer to format specification structure.

defaultPrecision Default precision of the value. For float, it is 6, for double it is 15.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.28 int rtXmlEncEmptyElement (OSCTXT * *pctxt*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*, OSBOOL *terminate*)

This function encodes an empty element tag value (<*elemName*/>).

Parameters

pctxt Pointer to context block structure.

elemName XML element name.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

terminate Add closing '>' character.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.29 int rtXmlEncEndDocument (OSCTXT **pctxt*)

This function adds trailer information and a null terminator at the end of the XML document being encoded.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.30 int rtXmlEncEndElement (OSCTXT **pctxt*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*)

This function encodes an end element tag value (</*elemName*>).

Parameters

pctxt Pointer to context block structure.

elemName XML element name.

pNS XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.31 int rtXmlEncEndSoapElems (OSCTXT **pctxt*, OSXMLSOAPMsgType *msgtype*)

This function encodes SOAP end element tags.

If will add a SOAP body or fault end tag based on the SOAP message type argument. It will then add an envelope end element tag.

Parameters

pctxt Pointer to context block structure.

msgtype SOAP message type (body, fault, or none)

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.32 int rtXmlEncEndSoapEnv (OSCTXT * *pctxt*)

This function encodes a SOAP envelope end element tag (<SOAP-ENV:Envelope/>).

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.33 int rtXmlEncFloat (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD float type.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

pFmtSpec Pointer to format specification structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.34 int rtXmlEncFloatAttr (OSCTXT * *pctxt*, OSREAL *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*, const OSDoubleFmt * *pFmtSpec*)

This function encodes a variable of the XSD float type as an attribute.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name. A name must be provided.

attrNameLen Length of XML attribute name.

pFmtSpec Pointer to format specification structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.35 int rtXmlEncGDay (OSCTXT **pctxt*, const OSXSDDateT ime **pvalue*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*)

This function encodes a numeric gDay element into an XML string representation.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.36 int rtXmlEncGDayValue (OSCTXT **pctxt*, const OSXSDDateT ime **pvalue*)

This function encodes a numeric gDay value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.37 int rtXmlEncGMonth (OSCTXT **pctxt*, const OSXSDDateT ime **pvalue*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*)

This function encodes a numeric gMonth element into an XML string representation.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.38 int rtXmlEncGMonthDay (OSCTXT * *pctxt*, const OSXSDDate Time * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gMonthDay element into an XML string representation.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.39 int rtXmlEncGMonthDayValue (OSCTXT * *pctxt*, const OSXSDDate Time * *pvalue*)

This function encodes a numeric gMonthDay value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.40 int rtXmlEncGMonthValue (OSCTXT * *pctxt*, const OSXSDDate Time * *pvalue*)

This function encodes a numeric gMonth value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.41 int rtXmlEncGYear (OSCTXT * *pctxt*, const OSXSDDateTIme * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gYear element into an XML string representation.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.42 int rtXmlEncGYearMonth (OSCTXT * *pctxt*, const OSXSDDateTIme * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a numeric gYearMonth element into an XML string representation.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.43 int rtXmlEncGYearMonthValue (OSCTXT * *pctxt*, const OSXSDDateTIme * *pvalue*)

This function encodes a numeric gYearMonth value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Pointer to value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.44 int rtXmlEncGYearValue (OSCTXT * *pctxt*, const OSXSDDateT * *pvalue*)

This function encodes a numeric gYear value into an XML string representation.

It just puts the encoded value into the buffer or stream without any tags.

Parameters

- pctxt*** Pointer to context block structure.
- pvalue*** Pointer to value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.45 int rtXmlEncHexBinary (OSCTXT * *pctxt*, OSSIZE *nocts*, const OSOCTET * *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD hexBinary type.

Parameters

- pctxt*** Pointer to context block structure.
- nocts*** Number of octets in the value string.
- value*** Value to be encoded.
- elemName*** XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS*** XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.46 int rtXmlEncHexBinaryAttr (OSCTXT * *pctxt*, OSUINT32 *nocts*, const OSOCTET * *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*)

This function encodes a variable of the XSD hexBinary type as an attribute.

Parameters

- pctxt*** Pointer to context block structure.
- nocts*** Number of octets in the value string.
- value*** Value to be encoded.
- attrName*** XML attribute name. A name must be provided.
- attrNameLen*** Length of XML attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.47 int rtXmlEncHexStrValue (OSCTXT **pctxt*, OSSIZE *nocts*, const OSOCTET **data*)

This function encodes a variable of the XSD hexBinary type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

- pctxt* Pointer to context block structure.
nocts Number of octets in the value string.
data Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.48 int rtXmlEncIndent (OSCTXT **pctxt*)

This function adds indentation whitespace to the output stream.

The amount of indentation to add is determined by the level member variable in the context structure and the OSXM-LINDET constant value.

Parameters

- pctxt* Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.49 int rtXmlEncInt (OSCTXT **pctxt*, OSINT32 *value*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*)

This function encodes a variable of the XSD integer type.

Parameters

- pctxt* Pointer to context block structure.
value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.50 int rtXmlEncInt64 (OSCTXT * *pctxt*, OSINT64 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD integer type.

This version of the function is used for 64-bit integer values.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.51 int rtXmlEncInt64Attr (OSCTXT * *pctxt*, OSINT64 *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*)

This function encodes a variable of the XSD integer type as an attribute (name="value").

This version of the function is used for 64-bit integer values.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name.

attrNameLen Length (in bytes) of the attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.52 int rtXmlEncInt64Value (OSCTXT **pctxt*, OSINT64 *value*)

This function encodes a variable of the XSD integer type.

This version of the function is used for 64-bit integer values. It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

- pctxt*** Pointer to context block structure.
- value*** Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.53 int rtXmlEncIntAttr (OSCTXT **pctxt*, OSINT32 *value*, const OSUTF8CHAR **attrName*, OSSIZE *attrNameLen*)

This function encodes a variable of the XSD integer type as an attribute (name="value").

Parameters

- pctxt*** Pointer to context block structure.
- value*** Value to be encoded.
- attrName*** XML attribute name.
- attrNameLen*** Length (in bytes) of the attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.54 int rtXmlEncIntPattern (OSCTXT **pctxt*, OSINT32 *value*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*, const OSUTF8CHAR **pattern*)

This function encodes a variable of the XSD integer type using a pattern to specify the format of the integer value.

Parameters

- pctxt*** Pointer to context block structure.
- value*** Value to be encoded.
- elemName*** XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS*** XML namespace information (prefix and URI).
- pattern*** Pattern of the encoded value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.55 int rtXmlEncIntValue (OSCTXT **pctxt*, OSINT32 *value*)

This function encodes a variable of the XSD integer type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.56 int rtXmlEncNamedBits (OSCTXT **pctxt*, const OSBitMapItem **pBitMap*, OSUINT32 *nbits*, const OSOCTET **pvalue*, const OSUTF8CHAR **elemName*, OSXMLNamespace **pNS*)

This function encodes a variable of the ASN.1 BIT STRING type.

In this case, a set of named bits was provided in the schema for the bit values. The encoding is a list of the named bit identifiers corresponding to each set bit in the bit string value.

Parameters

pctxt Pointer to context block structure.

pBitMap Bit map equating symbolic bit names to bit numbers.

nbits Number of bits in the sit string value.

pvalue Bit string value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.57 int rtXmlEncNSAttrs (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function encodes namespace declaration attributes at the beginning of an XML document.

The attributes to be encoded are stored in the namespace list provided, or within the context if a NULL pointer is passed for *pNSAttrs*. Namespaces are added to this list by using the namespace utility functions.

Parameters

- pctxt* Pointer to context block structure.
- pNSAttrs* Pointer to list of namespace attributes.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.58 int rtXmlEncReal10 (OSCTXT * *pctxt*, const OSUTF8CHAR * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the ASN.1 REAL base 10 type.

Parameters

- pctxt* A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.
- pvalue* A pointer to an REAL base 10 value.
- elemName* XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 (0) = success,
- negative return value is error.

6.2.2.59 int rtXmlEncSoapArrayTypeAttr (OSCTXT * *pctxt*, const OSUTF8CHAR * *name*, const OSUTF8CHAR * *value*, OSSIZE *itemCount*)

This function encodes the special SOAP encoding attrType attribute which specifies the number and type of elements in a SOAP array.

The form of this attribute is 'attrType="<type>[count]"'.

Parameters

- pctxt* Pointer to context block structure.
- name* Attribute name (NS prefix + arrayType)
- value* UTF-8 string value to be encoded.

itemCount Count of the number of elements in the array.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.60 int rtXmlEncStartDocument (OSCTXT * *pctxt*)

This function encodes the XML header text at the beginning of an XML document.

This is normally the following:

```
<?xml version="1.0" encoding="UTF-8"?>
```

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.61 int rtXmlEncStartElement (OSCTXT * *pctxt*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*, OSBOOL *terminate*)

This function encodes a start element tag value (<*elemName*>).

Parameters

pctxt Pointer to context block structure.

elemName XML element name. Empty string and null are treated equivalently.

pNS XML namespace information (prefix and URI). If the prefix is NULL, this method will search the context's namespace stack for a prefix to use.

pNSAttrs List of namespace attributes to be added to element.

terminate Add closing '>' character.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.62 int rtXmlEncStartSoapElems (OSCTXT * *pctxt*, OSXMLSOAPMsgType *msgtype*)

This function encodes a SOAP envelope start element tag and an optional SOAP body or fault tag.

This includes all of the standard SOAP namespace attributes.

Parameters

- pctxt* Pointer to context block structure.
- msgtype* SOAP message type (body, fault, or none)

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.63 int rtXmlEncStartSoapEnv (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function encodes a SOAP envelope start element tag.

This includes all of the standard SOAP namespace attributes.

Parameters

- pctxt* Pointer to context block structure.
- pNSAttrs* List of namespace attributes to be added to SOAP envelope.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.64 int rtXmlEncString (OSCTXT * *pctxt*, OSXMLSTRING * *pxmlstr*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD string type.

Parameters

- pctxt* Pointer to context block structure.
- pxmlstr* XML string value to be encoded.
- elemName* XML element name. If either null or empty string is passed, no element tag is added to the encoded value.
- pNS* XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.65 int rtXmlEncStringValue (OSCTXT **pctxt*, const OSUTF8CHAR **value*)

This function encodes a variable of the XSD string type.

Parameters

- pctxt* Pointer to context block structure.
- value* XML string value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.66 int rtXmlEncStringValue2 (OSCTXT **pctxt*, const OSUTF8CHAR **value*, OSSIZE *valueLen*)

This function encodes a variable of the XSD string type.

Parameters

- pctxt* Pointer to context block structure.
- value* XML string value to be encoded.
- valueLen* UTF-8 string value length (in octets).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.67 int rtXmlEncTermStartElement (OSCTXT **pctxt*)

This function terminates a currently open XML start element by adding either a '>' or '/>' (if empty) terminator.

It will also add XSI attributes to the element.

Parameters

- pctxt* Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.68 int rtXmlEncTime (OSCTXT * *pctxt*, const OSXSDDate Time * *pvalue*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD 'time' type as an string.

This version of the function is used to encode OSXSDDate Time value into any of following format in different condition as stated below. (1) hh-mm-ss.ss used if tz_flag = false (2) hh-mm-ss.ssZ used if tz_flag = false and tzo = 0 (3) hh-mm-ss.ss+HH:MM if tz_flag = false and tzo > 0 (4) hh-mm-ss.ss-HH:MM-HH:MM if tz_flag = false and tzo < 0

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDate Time type pointer points to a OSXSDDate Time value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS Pointer to namespace structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.69 int rtXmlEncTimeValue (OSCTXT * *pctxt*, const OSXSDDate Time * *pvalue*)

This function encodes a variable of the XSD 'time' type as an string.

This version of the function just puts the encoded value in the destination buffer or stream without any tags.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDate Time type pointer points to a OSXSDDate Time value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.70 int rtXmlEncUInt (OSCTXT * *pctxt*, OSUINT32 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD unsigned integer type.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.71 int rtXmlEncUInt64 (OSCTXT * *pctxt*, OSUINT64 *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a variable of the XSD integer type.

This version of the function is used when constraints cause an unsigned 64-bit integer variable to be used.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.72 int rtXmlEncUInt64Attr (OSCTXT * *pctxt*, OSUINT64 *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*)

This function encodes a variable of the XSD integer type as an attribute (name="value").

This version of the function is used for unsigned 64-bit integer values.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

attrName XML attribute name.

attrNameLen Length (in bytes) of the attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.73 int rtXmlEncUInt64Value (OSCTXT * *pctxt*, OSUINT64 *value*)

This function encodes a variable of the XSD integer type.

This version of the function is used when constraints cause an unsigned 64-bit integer variable to be used. It writes the encoded value to the destination buffer or stream without any tags.

Parameters

pctxt Pointer to context block structure.
value Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.74 int rtXmlEncUIntAttr (OSCTXT * *pctxt*, OSUINT32 *value*, const OSUTF8CHAR * *attrName*, OSSIZE *attrNameLen*)

This function encodes a variable of the XSD unsigned integer type as an attribute (name="value").

Parameters

pctxt Pointer to context block structure.
value Value to be encoded.
attrName XML attribute name.
attrNameLen Length (in bytes) of the attribute name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.75 int rtXmlEncUIntValue (OSCTXT * *pctxt*, OSUINT32 *value*)

This function encodes a variable of the XSD unsigned integer type.

It just puts the encoded value in the destination buffer or stream without any tags.

Parameters

pctxt Pointer to context block structure.
value Value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.76 int rtXmlEncUnicodeStr (OSCTXT * *pctxt*, const OSUNICHAR * *value*, OSSIZE *nchars*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a Unicode string value.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded. This is a pointer to an array of 16-bit integer values.

nchars Number of characters in value array.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.77 int rtXmlEncUTF8Attr (OSCTXT * *pctxt*, const OSUTF8CHAR * *name*, const OSUTF8CHAR * *value*)

This function encodes an attribute in which the name and value are given as a null-terminated UTF-8 strings.

Parameters

pctxt Pointer to context block structure.

name Attribute name.

value UTF-8 string value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.78 int rtXmlEncUTF8Attr2 (OSCTXT * *pctxt*, const OSUTF8CHAR * *name*, OSSIZE *nameLen*, const OSUTF8CHAR * *value*, OSSIZE *valueLen*)

This function encodes an attribute in which the name and value are given as a UTF-8 strings with lengths.

Parameters

pctxt Pointer to context block structure.

name Attribute name.

nameLen Attribute name length (in octets).

value UTF-8 string value to be encoded.

valueLen UTF-8 string value length (in octets).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.79 int rtXmlEncUTF8Str (OSCTXT * *pctxt*, const OSUTF8CHAR * *value*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*)

This function encodes a UTF-8 string value.

Parameters

pctxt Pointer to context block structure.

value Value to be encoded.

elemName XML element name. A name must be provided. If an empty string is passed (""), no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.80 int rtXmlEncXSIAttrs (OSCTXT * *pctxt*, OSBOOL *needXSI*)

This function encodes XML schema instance (XSI) attributes at the beginning of an XML document.

The encoded attributes include the XSI namespace declaration, the XSD schema location attribute, and the XSD no namespace schema location attribute.

The XSI namespace declaration will only be added to the document if schema location attributes exist or the 'needXSI' flag (see below) is set.

Parameters

pctxt Pointer to context block structure.

needXSI This flag is set to true to indicate the XSI namespace declaration is required to support XML items in the main document body such as xsi:type or xsi:nil.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.81 int rtXmlEncXSINilAttr (OSCTXT * *pctxt*)

This function encodes an XML nil attribute (xsi:nil="true").

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.82 int rtXmlEncXSITypeAttr (OSCTXT * *pctxt*, const OSUTF8CHAR * *value*)

This function encodes an XML schema instance (XSI) type attribute value (xsi:type="value").

Parameters

pctxt Pointer to context block structure.

value XSI type attribute value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.83 int rtXmlEncXSITypeAttr2 (OSCTXT * *pctxt*, const OSUTF8CHAR * *typeNsUri*, const OSUTF8CHAR * *typeName*)

This function encodes an XML schema instance (XSI) type attribute value (xsi:type="pfx:value").

This will encode namespace declarations for the xsi namespace and for the typeNsUri namespace, if needed.

Parameters

pctxt Pointer to context block structure.

typeNsUri The type's namespace URI. Either null or empty if none.

typeName The type's name.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.84 int rtXmlFreeInputSource (OSCTXT * *pctxt*)

This function closes an input source that was previously created with one of the create input source functions such as 'rtXmlCreateFileInputSource'.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.85 int rtXmlGetIndent (OSCTXT * *pctxt*)

This function returns current XML output indent value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

Current indent value (≥ 0) if OK, negative status code if error.

6.2.2.86 int rtXmlGetIndentChar (OSCTXT * *pctxt*)

This function returns current XML output indent character value (default is space).

Parameters

pctxt Pointer to OSCTXT structure

Returns

Current indent character (> 0) if OK, negative status code if error.

6.2.2.87 OSBOOL rtXmlGetWriteBOM (OSCTXT * *pctxt*)

This function returns whether the Unicode byte order mark will be encoded.

Parameters

pctxt Pointer to OSCTXT structure.

Returns

TRUE if BOM is to be encoded, FALSE if not or if context uninitialized.

6.2.2.88 int rtXmlPrintNSAttrs (const char * *name*, const OSRTDList * *data*)

This function prints a list of namespace attributes.

Parameters

name Name to print.

data List of namespace attributes.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.2.2.89 int rtXmlSetEncBufPtr (OSCTXT * *pctxt*, OSOCTET * *bufaddr*, OSSIZE *bufsiz*)

This function is used to set the internal buffer within the run-time library encoding context.

It must be called after the context variable is initialized by the rtxInitContext function and before any other compiler generated or run-time library encode function.

This function should not be called with a context that has an associated stream open, but if it is, the stream may be automatically closed.

Parameters

pctxt Pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

bufaddr A pointer to a memory buffer to use to encode a message. The buffer should be declared as an array of unsigned characters (OCTETS). This parameter can be set to NULL to specify dynamic encoding (i.e., the encode functions will dynamically allocate a buffer to hold the encoded message).

bufsiz The length of the memory buffer in bytes. Should be set to zero if NULL was specified for bufaddr (i.e. dynamic encoding was selected).

6.3 XML utility functions.

Functions

- int **rtXmlWriteToFile** (OSCTXT *pctxt, const char *filename)

This function writes the encoded XML message stored in the context message buffer out to a file.

6.3.1 Function Documentation

6.3.1.1 int rtXmlWriteToFile (OSCTXT **pctxt*, const char **filename*)

This function writes the encoded XML message stored in the context message buffer out to a file.

Parameters

pctxt Pointer to OSCTXT structure.

filename Full path to file to which XML is to be written.

Returns

0 - if success, negative value if error.

6.4 XML pull-parser decode functions.

Functions

- int **rtXmlpDecAny** (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int **rtXmlpDecAny2** (OSCTXT *pctxt, OSUTF8CHAR **pvalue)
This version of the rtXmlpDecAny function returns the string in a mutable buffer.
- int **rtXmlpDecAnyAttrStr** (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrStr, OSSIZE attrIndex)
This function decodes an any attribute string.
- int **rtXmlpDecAnyElem** (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int **rtXmlpDecBase64Str** (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocnts, OSSIZE bufsize)
This function decodes a contents of a Base64-encode binary string into a static memory structure.
- int **rtXmlpDecBigInt** (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function will decode a variable of the XSD integer type.
- int **rtXmlpDecBitString** (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes a bit string value.
- int **rtXmlpDecBool** (OSCTXT *pctxt, OSBOOL *pvalue)
This function decodes a variable of the boolean type.
- int **rtXmlpDecDate** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'date' type.
- int **rtXmlpDecDateTime** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'dateTime' type.
- int **rtXmlpDecDecimal** (OSCTXT *pctxt, OSREAL *pvalue, int totalDigits, int fractionDigits)
This function decodes the contents of a decimal data type.
- int **rtXmlpDecDouble** (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a float or double data type.
- int **rtXmlpDecDoubleExt** (OSCTXT *pctxt, OSUINT8 flags, OSREAL *pvalue)
This function decodes the contents of a float or double data type.
- int **rtXmlpDecDynBase64Str** (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a Base64-encode binary string.
- int **rtXmlpDecDynBitString** (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a bit string value.
- int **rtXmlpDecDynHexStr** (OSCTXT *pctxt, OSDynOctStr *pvalue)

This function decodes a contents of a hexBinary string.

- int [rtXmlpDecDynUnicodeStr](#) (OSCTXT *pctxt, const OSUNICHAR **ppdata, OSSIZE *pnchars)
This function decodes a Unicode string data type.
- int [rtXmlpDecDynUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR **outdata)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlpDecUTF8Str](#) (OSCTXT *pctxt, OSUTF8CHAR *out, OSSIZE max_len)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlpDecGDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gDay' type.
- int [rtXmlpDecGMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonth' type.
- int [rtXmlpDecGMonthDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonthDay' type.
- int [rtXmlpDecGYear](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int [rtXmlpDecGYearMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int [rtXmlpDecHexStr](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int [rtXmlpDecInt](#) (OSCTXT *pctxt, OSINT32 *pvalue)
This function decodes the contents of a 32-bit integer data type.
- int [rtXmlpDecInt8](#) (OSCTXT *pctxt, OSINT8 *pvalue)
This function decodes the contents of an 8-bit integer data type (i.e.
- int [rtXmlpDecInt16](#) (OSCTXT *pctxt, OSINT16 *pvalue)
This function decodes the contents of a 16-bit integer data type.
- int [rtXmlpDecInt64](#) (OSCTXT *pctxt, OSINT64 *pvalue)
This function decodes the contents of a 64-bit integer data type.
- int [rtXmlpDecNamedBits](#) (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes the contents of a named bit field.
- int [rtXmlpDecStrList](#) (OSCTXT *pctxt, OSRTDList *plist)
This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.
- int [rtXmlpDecTime](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'time' type.

- int **rtXmlpDecUInt** (OSCTXT *pctxt, OSUINT32 *pvalue)
This function decodes the contents of an unsigned 32-bit integer data type.
- int **rtXmlpDecUInt8** (OSCTXT *pctxt, OSOCTET *pvalue)
This function decodes the contents of an unsigned 8-bit integer data type (i.e.
- int **rtXmlpDecUInt16** (OSCTXT *pctxt, OSUINT16 *pvalue)
This function decodes the contents of an unsigned 16-bit integer data type.
- int **rtXmlpDecUInt64** (OSCTXT *pctxt, OSUINT64 *pvalue)
This function decodes the contents of an unsigned 64-bit integer data type.
- int **rtXmlpDecXmlStr** (OSCTXT *pctxt, OSXMLSTRING *outdata)
This function decodes the contents of an XML string data type.
- int **rtXmlpDecXmlStrList** (OSCTXT *pctxt, OSRTDList *plist)
This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.
- int **rtXmlpDecXSIAttr** (OSCTXT *pctxt, const OSXMLNameFragments *attrName)
This function decodes XSI (XML Schema Instance) attributes that may be present in any arbitrary XML element within a document.
- int **rtXmlpDecXSITypeAttr** (OSCTXT *pctxt, const OSXMLNameFragments *attrName, const OS-UTF8CHAR **ppAttrValue)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).
- int **rtXmlpGetAttributeID** (const OSXMLStrFragment *attrName, OSINT16 nsidx, OSSIZE nAttr, const OS-XMLAttrDescr attrNames[], OSUINT32 attrPresent[])
This function finds an attribute in the descriptor table.
- int **rtXmlpGetNextElem** (OSCTXT *pctxt, OSXMLElemDescr *pElem, OSINT32 level)
This function parse the next element start tag.
- int **rtXmlpGetNextElemID** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nRows, OSINT32 level, OSBOOL continueParse)
This function parses the next start tag and finds the index of the element name in the descriptor table.
- int **rtXmlpMarkLastEventActive** (OSCTXT *pctxt)
This function marks current tag as unprocessed.
- int **rtXmlpMatchStartTag** (OSCTXT *pctxt, const OSUTF8CHAR *elemLocalName, OSINT16 nsidx)
This function parses the next start tag that matches with given name.
- int **rtXmlpMatchEndTag** (OSCTXT *pctxt, OSINT32 level)
This function parse next end tag that matches with given name.
- OSBOOL **rtXmlpHasAttributes** (OSCTXT *pctxt)
This function checks accessibility of attributes.
- int **rtXmlpGetAttributeCount** (OSCTXT *pctxt)

This function returns number of attributes in last processed start tag.

- int **rtXmlpSelectAttribute** (OSCTXT *pctxt, OSXMLNameFragments *pAttr, OSINT16 *nsidx, OSSIZE attrIndex)

This function selects attribute to decode.

- OSINT32 **rtXmlpGetCurrentLevel** (OSCTXT *pctxt)

This function returns current nesting level.

- void **rtXmlpSetWhiteSpaceMode** (OSCTXT *pctxt, **OSXMLWhiteSpaceMode** whiteSpaceMode)

Sets the whitespace treatment mode.

- OSBOOL **rtXmlpSetMixedContentMode** (OSCTXT *pctxt, OSBOOL mixedContentMode)

Sets mixed content mode.

- void **rtXmlpSetListMode** (OSCTXT *pctxt)

Sets list mode.

- OSBOOL **rtXmlpListHasItem** (OSCTXT *pctxt)

Check for end of decoded token list.

- void **rtXmlpCountListItems** (OSCTXT *pctxt, OSSIZE *itemCnt)

Count tokens in list.

- int **rtXmlpGetNextSeqElemID2** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, const **OSXMLGroupDesc** *pGroup, int groups, int curID, int lastMandatoryID, OSBOOL groupMode, OSBOOL checkRepeat)

This function parses the next start tag and finds index of element name in descriptor table.

- int **rtXmlpGetNextSeqElemID** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, const **OSXMLGroupDesc** *pGroup, int curID, int lastMandatoryID, OSBOOL groupMode)

This function parses the next start tag and finds index of element name in descriptor table.

- int **rtXmlpGetNextSeqElemIDExt** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, const **OSXMLGroupDesc** *ppGroup, const OSBOOL *extRequired, int postExtRootID, int curID, int lastMandatoryID, OSBOOL groupMode)

This is an ASN.1 extension-supporting version of rtXmlpGetNextSeqElemID.

- int **rtXmlpGetNextAllElemID** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nRows, const OSUINT8 *pOrder, OSSIZE nOrder, OSSIZE maxOrder, int anyID)

This function parses the next start tag and finds index of element name in descriptor table.

- int **rtXmlpGetNextAllElemID16** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nRows, const OSUINT16 *pOrder, OSSIZE nOrder, OSSIZE maxOrder, int anyID)

This function parses the next start tag and finds index of element name in descriptor table.

- int **rtXmlpGetNextAllElemID32** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nRows, const OSUINT32 *pOrder, OSSIZE nOrder, OSSIZE maxOrder, int anyID)

This function parses the next start tag and finds index of element name in descriptor table.

- void **rtXmlpSetNamespaceTable** (OSCTXT *pctxt, const OSUTF8CHAR *namespaceTable[], OSSIZE nmNamespaces)

Sets user namespace table.

- int [rtXmlpCreateReader](#) (OSCTXT *pctxt)
Creates pull parser reader structure within the context.
- void [rtXmlpHideAttributes](#) (OSCTXT *pctxt)
Disable access to attributes.
- OSBOOL [rtXmlpNeedDecodeAttributes](#) (OSCTXT *pctxt)
This function checks if attributes were previously decoded.
- void [rtXmlpMarkPos](#) (OSCTXT *pctxt)
Save current decode position.
- void [rtXmlpRewindToMarkedPos](#) (OSCTXT *pctxt)
Rewind to saved decode position.
- void [rtXmlpResetMarkedPos](#) (OSCTXT *pctxt)
Reset saved decode position.
- int [rtXmlpGetXSITypeAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrValue, OSINT16 *nsidx, OSSIZE *pLocalOffs)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).
- int [rtXmlpGetXmAttrs](#) (OSCTXT *pctxt, OSRTDList *pNSAttrs)
This function decodes namespace attributes from start tag and adds them to the given list.
- int [rtXmlpDecXSIAttrs](#) (OSCTXT *pctxt)
This function decodes XSI (XML Schema Instance) that may be present in any arbitrary XML element within a document.
- OSBOOL [rtXmlpIsEmptyElement](#) (OSCTXT *pctxt)
Check element content: empty or not.
- int [rtXmlEncAttrC14N](#) (OSCTXT *pctxt)
This function used only in C14 mode.
- struct OSXMLReader * [rtXmlpGetReader](#) (OSCTXT *pctxt)
This function fetches the XML reader structure from the context for use in low-level pull parser calls.
- OSBOOL [rtXmlpIsLastEventDone](#) (OSCTXT *pctxt)
Check processing status of current tag.
- int [rtXmlpGetXSITypeIndex](#) (OSCTXT *pctxt, const OSXMLItemDescr typetab[], OSSIZE typetabsiz)
This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type) and find type index in descriptor table.
- int [rtXmlpLookupXSITypeIndex](#) (OSCTXT *pctxt, const OSUTF8CHAR *pXsiType, OSINT16 xsiTypeIdx, const OSXMLItemDescr typetab[], OSSIZE typetabsiz)
This function find index of XSI (XML Schema Instance) type in descriptor table.
- void [rtXmlpForceDecodeAsGroup](#) (OSCTXT *pctxt)

Disable skipping of unknown elements in optional sequence tail.

- OSBOOL [rtXmlpIsDecodeAsGroup](#) (OSCTXT *pctxt)
This function checks if "decode as group" mode was forced.
- OSBOOL [rtXmlpIsUTF8Encoding](#) (OSCTXT *pctxt)
This function checks if the encoding specified in XML header is UTF-8.
- int [rtXmlpReadBytes](#) (OSCTXT *pctxt, OSOCTET *pbuf, OSSIZE nbytes)
This function reads the specified number of bytes directly from the underlying XML parser stream.

6.4.1 Function Documentation

6.4.1.1 int [rtXmlEncAttrC14N](#) (OSCTXT * *pctxt*)

This function used only in C14 mode.

It provide attributes sorting.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.2 void [rtXmlpCountListItems](#) (OSCTXT * *pctxt*, OSSIZE * *itemCnt*)

Count tokens in list.

Parameters

pctxt Pointer to context block structure.

itemCnt Pointer to number of elements in list.

Returns

Token number. For element content function check accessed part of content only. Returned value may be below then real token number.

6.4.1.3 int [rtXmlpCreateReader](#) (OSCTXT * *pctxt*)

Creates pull parser reader structure within the context.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.4 int rtXmlpDecAny (OSCTXT * *pctxt*, const OSUTF8CHAR ** *pvalue*)

This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).

The decoded XML fragment is returned as a string in the form as it appears in the document. Memory is allocated for the string using the rtxMemAlloc function.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to UTF8 character string pointer to receive decoded XML fragment. Memory is allocated for the string using the run-time memory manager.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.5 int rtXmlpDecAny2 (OSCTXT * *pctxt*, OSUTF8CHAR ** *pvalue*)

This version of the rtXmlpDecAny function returns the string in a mutable buffer.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to UTF8 character string pointer to receive decoded XML fragment. Memory is allocated for the string using the run-time memory manager.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.6 int rtXmlpDecAnyAttrStr (OSCTXT * *pctxt*, const OSUTF8CHAR ** *ppAttrStr*, OSSIZE *attrIndex*)

This function decodes an any attribute string.

The full attribute string (name="value") is decoded and returned on the string output argument. Memory is allocated for the string using the rtxMemAlloc function.

Parameters

pctxt Pointer to context block structure.

ppAttrStr Pointer to UTF8 character string pointer to receive decoded attribute string. Memory is allocated for the string using the run-time memory manager.

attrIndex Index of attribute.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.7 int rtXmlpDecAnyElem (OSCTXT * *pctxt*, const OSUTF8CHAR ** *pvalue*)

This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).

The decoded XML fragment is returned as a string in the form as it appears in the document. Memory is allocated for the string using the rtxMemAlloc function. The difference between this function and rtXmlpDecAny is that this function preserves the full encoded XML fragment including the start and end elements tags and attributes. rtXmlpDecAny decodes the contents within the start and end tags.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to UTF8 character string pointer to receive decoded XML fragment. Memory is allocated for the string using the run-time memory manager.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.8 int rtXmlpDecBase64Str (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSSIZE *bufsize*)

This function decodes a contents of a Base64-encode binary string into a static memory structure.

The octet string must be Base64 encoded. This function call is used to decode a sized base64Binary string production. Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the bufsize input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.9 int rtXmlpDecBigInt (OSCTXT * *pctxt*, const OSUTF8CHAR ** *pvalue*)

This function will decode a variable of the XSD integer type.

In this case, the integer is assumed to be of a larger size than can fit in a C or C++ long type (normally 32 or 64 bits). For example, parameters used to calculate security values are typically larger than these sizes.

These variables are stored in character string constant variables. The radix should be 10. If it is necessary to convert to another radix, then use rtxBigIntSetStr or rtxBigIntToString functions. Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to a pointer to receive decoded UTF-8 string. Dynamic memory is allocated for the variable using the rtMemAlloc function. The decoded variable is represented as a string starting with appropriate prefix.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.10 int rtXmlpDecBitString (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnbits*, OSUINT32 *bufsize*)

This function decodes a bit string value.

The string consists of a series of '1' and '0' characters. This is the static version in which the user provides a pre-allocated memory buffer to receive the decoded data. One byte in a memory buffer can hold 8 characters of encoded data. Bits are stored from MSB to LSB order.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

pnbits Pointer to hold decoded number of bits.

bufsize Size of buffer passed in *pvalue* argument.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.11 int rtXmlpDecBool (OSCTXT * *pctxt*, OSBOOL * *pvalue*)

This function decodes a variable of the boolean type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.12 int rtXmlpDecDate (OSCTXT * *pctxt*, OSXSDDateType * *pvalue*)

This function decodes a variable of the XSD 'date' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have CCYY-MM-DD format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateType type pointer points to a OSXSDDateType value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.13 int rtXmlpDecDateTime (OSCTXT * *pctxt*, OSXSDDateType * *pvalue*)

This function decodes a variable of the XSD 'dateTime' type.

Input is expected to be a string of characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateType type pointer points to a OSXSDDateType value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.14 int rtXmlpDecDecimal (OSCTXT * *pctxt*, OSREAL * *pvalue*, int *totalDigits*, int *fractionDigits*)

This function decodes the contents of a decimal data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

totalDigits Number of total digits in the decimal number from XSD totalDigits facet value. Argument should be set to -1 if facet not given.

fractionDigits Number of fraction digits in the decimal number from XSD fractionDigits facet value. Argument should be set to -1 if facet not given.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.15 int rtXmlpDecDouble (OSCTXT * *pctxt*, OSREAL * *pvalue*)

This function decodes the contents of a float or double data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit double value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.16 int rtXmlpDecDoubleExt (OSCTXT * *pctxt*, OSUINT8 *flags*, OSREAL * *pvalue*)

This function decodes the contents of a float or double data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

flags Specifies alternatives allowed in the lexical value. See OSXMLREALENC* constants. bit 0 (rightmost) set: recognize INF, -INF, NaN text values bit 1 set: recognize leading '+' on normal reals bit 2 set: recognize leading '+' on INF bit 3 set: recognize leading zeros in exponent bit 4 set: recognize exponents

pvalue Pointer to 64-bit double value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.17 int rtXmlpDecDynBase64Str (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a contents of a Base64-encode binary string.

The octet string must be Base64 encoded. This function will allocate dynamic memory to store the decoded result. Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated for the string using the rtxMemAlloc function.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.18 int rtXmlpDecDynBitString (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a bit string value.

The string consists of a series of '1' and '0' characters. This is the dynamic version in which memory is allocated for the returned binary string variable. Bits are stored from MSB to LSB order.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to a variable to receive the decoded boolean value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.19 int rtXmlpDecDynHexStr (OSCTXT * *pctxt*, OSDynOctStr * *pvalue*)

This function decodes a contents of a hexBinary string.

This function will allocate dynamic memory to store the decoded result. Input is expected to be a string of OS-UTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a dynamic octet string structure to receive the decoded octet string. Dynamic memory is allocated to hold the string using the rtxMemAlloc function.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.20 int rtXmlpDecDynUnicodeStr (OSCTXT * *pctxt*, const OSUNICHAR ** *ppdata*, OSSIZE * *pnchars*)

This function decodes a Unicode string data type.

The input is assumed to be in UTF-8 format. This function reads each character and converts it into its Unicode equivalent.

Parameters

pctxt Pointer to context block structure.

ppdata Pointer to Unicode character string. A Unicode character string is represented as an array of unsigned 16-bit integers in C. Memory is allocated for the string using the run-time memory manager.

pnchars Pointer to integer variables to receive the number of characters in the string.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.21 int rtXmlpDecDynUTF8Str (OSCTXT * *pctxt*, const OSUTF8CHAR ** *outdata*)

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

outdata Pointer to a pointer to receive decoded UTF-8 string. Memory is allocated for this string using the run-time memory manager.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.22 int rtXmlpDecGDay (OSCTXT * *pctxt*, OSXSDDate Time * *pvalue*)

This function decodes a variable of the XSD 'gDay' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have ---DD[-+hh:mm]Z format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDate type pointer points to a OSXSDDate value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.23 int rtXmlpDecGMonth (OSCTXT * *pctxt*, OSXSDDate * *pvalue*)

This function decodes a variable of the XSD 'gMonth' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have --MM[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDate type pointer points to a OSXSDDate value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.24 int rtXmlpDecGMonthDay (OSCTXT * *pctxt*, OSXSDDate * *pvalue*)

This function decodes a variable of the XSD 'gMonthDay' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have --MM-DD[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDate type pointer points to a OSXSDDate value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.25 int rtXmlpDecGYear (OSCTXT * *pctxt*, OSXSDDateTIme * *pvalue*)

This function decodes a variable of the XSD 'gYear' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have CCYY[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateTIme type pointer points to a OSXSDDateTIme value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.26 int rtXmlpDecGYearMonth (OSCTXT * *pctxt*, OSXSDDateTIme * *pvalue*)

This function decodes a variable of the XSD 'gYearMonth' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have CCYY-MM[-+hh:mm|Z] format.

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDateTIme type pointer points to a OSXSDDateTIme value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.27 int rtXmlpDecHexStr (OSCTXT * *pctxt*, OSOCTET * *pvalue*, OSUINT32 * *pnocts*, OSINT32 *bufsize*)

This function decodes the contents of a hexBinary string into a static memory structure.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

pvalue A pointer to a variable to receive the decoded bit string. This is assumed to be a static array large enough to hold the number of octets specified in the bufsize input parameter.

pnocts A pointer to an integer value to receive the decoded number of octets.

bufsize The size (in octets) of the sized octet string. An error will occur if the number of octets in the decoded string is larger than this value.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.28 int rtXmlpDecInt (OSCTXT **pctxt*, OSINT32 **pvalue*)

This function decodes the contents of a 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 32-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.29 int rtXmlpDecInt16 (OSCTXT **pctxt*, OSINT16 **pvalue*)

This function decodes the contents of a 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 16-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.30 int rtXmlpDecInt64 (OSCTXT **pctxt*, OSINT64 **pvalue*)

This function decodes the contents of a 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 64-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.31 int rtXmlpDecInt8 (OSCTXT * *pctxt*, OSINT8 * *pvalue*)

This function decodes the contents of an 8-bit integer data type (i.e.

a signed byte type in the range of -128 to 127). Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to 8-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.32 int rtXmlpDecNamedBits (OSCTXT * *pctxt*, const OSBitMapItem * *pBitMap*, OSOCTET * *pvalue*, OSUINT32 * *pnbits*, OSUINT32 *bufsize*)

This function decodes the contents of a named bit field.

This is a space-separated list of token values in which each token corresponds to a bit field in a bit map.

Parameters

pctxt Pointer to context block structure.

pBitMap Pointer to bit map structure that defined token to bit mappings.

pvalue Pointer to buffer to recieve decoded bit map.

pnbits Number of bits in decoded bit map.

bufsize Size of buffer passed in to received decoded bit values.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.33 int rtXmlpDecStrList (OSCTXT * *pctxt*, OSRTDList * *plist*)

This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.

Memory is allocated for the list nodes and token values using the rtx memory management functions.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

plist A pointer to a linked list structure to which the parsed token values will be added.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.34 int rtXmlpDecTime (OSCTXT * *pctxt*, OSXSDDate Time * *pvalue*)

This function decodes a variable of the XSD 'time' type.

Input is expected to be a string of characters returned by an XML pull parser. The string should have one of following formats:

(1) hh-mm-ss.ss used if tz_flag = false (2) hh-mm-ss.ssZ used if tz_flag = false and tzo = 0 (3) hh-mm-ss.ss.ss+HH:MM if tz_flag = false and tzo > 0 (4) hh-mm-ss.ss-HH:MM-HH:MM if tz_flag = false and tzo < 0

Parameters

pctxt Pointer to context block structure.

pvalue OSXSDDate Time type pointer points to a OSXSDDate Time value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.35 int rtXmlpDecUInt (OSCTXT * *pctxt*, OSUINT32 * *pvalue*)

This function decodes the contents of an unsigned 32-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 32-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.36 int rtXmlpDecUInt16 (OSCTXT **pctxt*, OSUINT16 **pvalue*)

This function decodes the contents of an unsigned 16-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 16-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.37 int rtXmlpDecUInt64 (OSCTXT **pctxt*, OSUINT64 **pvalue*)

This function decodes the contents of an unsigned 64-bit integer data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 64-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.38 int rtXmlpDecUInt8 (OSCTXT **pctxt*, OSOCTET **pvalue*)

This function decodes the contents of an unsigned 8-bit integer data type (i.e.

a signed byte type in the range of 0 to 255). Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

pctxt Pointer to context block structure.

pvalue Pointer to unsigned 8-bit integer value to receive decoded result.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.39 int rtXmlpDecUTF8Str (OSCTXT * *pctxt*, OSUTF8CHAR * *out*, OSSIZE *max_len*)

This function decodes the contents of a UTF-8 string data type.

Input is expected to be a string of OSUTF8CHAR characters returned by an XML pull parser.

Parameters

- pctxt*** Pointer to context block structure.
- out*** Pointer to an array of OSUTF8CHAR to receive decoded UTF-8 string.
- max_len*** Length of out array.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.40 int rtXmlpDecXmlStr (OSCTXT * *pctxt*, OSXMLSTRING * *outdata*)

This function decodes the contents of an XML string data type.

This type contains a pointer to a UTF-8 character string plus flags that can be set to alter the encoding of the string (for example, the cdata flag allows the string to be encoded in a CDATA section). Input is expected to be a string of UTF-8 characters returned by an XML parser.

Parameters

- pctxt*** Pointer to context block structure.
- outdata*** Pointer to an XML string structure to receive the decoded string. Memory is allocated for the string using the run-time memory manager.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.41 int rtXmlpDecXmlStrList (OSCTXT * *pctxt*, OSRTDList * *plist*)

This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.

Memory is allocated for the list nodes and token values using the rtx memory management functions. List contains OSXMLSTRING structures.

Parameters

- pctxt*** A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.
- plist*** A pointer to a linked list structure to which the parsed token values will be added.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.42 int rtXmlpDecXSIAttr (OSCTXT * *pctxt*, const OSXMLNameFragments * *attrName*)

This function decodes XSI (XML Schema Instance) attributes that may be present in any arbitrary XML element within a document.

Parameters

- pctxt* A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.
- attrName* A pointer to a structure holding various parts of an attribute name. The parts are in the form of string fragments meaning they are not null terminated. The user must be careful to use the value and length when working with them.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.43 int rtXmlpDecXSIAttrs (OSCTXT * *pctxt*)

This function decodes XSI (XML Schema Instance) that may be present in any arbitrary XML element within a document.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.44 int rtXmlpDecXSITypeAttr (OSCTXT * *pctxt*, const OSXMLNameFragments * *attrName*, const OSUTF8CHAR ** *ppAttrValue*)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).

Parameters

- pctxt* A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.
- attrName* A pointer to a structure holding various parts of an attribute name. The parts are in the form of string fragments meaning they are not null terminated. The user must be careful to use the value and length when working with them.

ppAttrValue A pointer to a pointer to a UTF8 character string to received the decoded XSI type name.

Returns

Completion status of operation:

- 0 = success,
- 1 = OK, but attrName was not xsi:type (i.e. no attribute match)
- negative return value is error.

6.4.1.45 void rtXmlpForceDecodeAsGroup (OSCTXT * *pctxt*)

Disable skipping of unknown elements in optional sequence tail.

Function used in outer types to break decode on first unknown element after decoding mandatory sequence part.

Parameters

pctxt Pointer to context block structure.

6.4.1.46 int rtXmlpGetAttributeCount (OSCTXT * *pctxt*)

This function returns number of attributes in last processed start tag.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- zero or positive value is attributes number,
- negative return value is error.

6.4.1.47 int rtXmlpGetAttributeID (const OSXMLStrFragment * *attrName*, OSINT16 *nsidx*, OSSIZE *nAttr*, const OSXMLAttrDescr *attrNames*[], OSUINT32 *attrPresent*[])

This function finds an attribute in the descriptor table.

Parameters

attrName A pointer to a structure holding various parts of an attribute name. The parts are in the form of string fragments meaning they are not null terminated. The user must be careful to use the value and length when working with them.

nsidx Namespace index:

- 0 = attribute is unqualified,
- positive value is user namespace from generated namespace table,
- negative value is predefined namespace like XSD instance and ect.

nAttr Number of descriptors in table.

attrNames Attributes descriptor table.

attrPresent Bit array to mark already decoded attributes. It is used to identify duplicate attributes.

Returns

Completion status of operation:

- positive or zero return value is attribute index in descriptor table,
- negative return value is error.

6.4.1.48 OSINT32 rtXmlpGetCurrentLevel (OSCTXT * *pctxt*)

This function returns current nesting level.

Parameters

pctxt Pointer to context block structure.

Returns

Current nesting level.

6.4.1.49 int rtXmlpGetNextAllElemID (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, OSSIZE *nrows*, const OSUINT8 * *pOrder*, OSSIZE *nOrder*, OSSIZE *maxOrder*, int *anyID*)

This function parses the next start tag and finds index of element name in descriptor table.

It used for decode "all" content model in strict mode.

Parameters

pctxt Pointer to context block structure.

tab Elements descriptor table.

nrows Number of descriptors in table.

pOrder Pointer to array to receive elements order.

nOrder Last element's index in order array.

maxOrder Size of order array.

anyID Identifier of xsd:any element.

Returns

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

6.4.1.50 int rtXmlpGetNextAllElemID16 (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, OSSIZE *nrows*, const OSUINT16 * *pOrder*, OSSIZE *nOrder*, OSSIZE *maxOrder*, int *anyID*)

This function parses the next start tag and finds index of element name in descriptor table.

It used for decode "all" content model in strict mode. This variant used when xsd:all has above 256 elements.

Parameters

pctxt Pointer to context block structure.
tab Elements descriptor table.
nrows Number of descriptors in table.
pOrder Pointer to array to receive elements order.
nOrder Last element's index in order array.
maxOrder Size of order array.
anyID Identifier of xsd:any element.

Returns

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

6.4.1.51 int rtXmlpGetNextAllElemID32 (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, OSSIZE *nrows*, const OSUINT32 * *pOrder*, OSSIZE *nOrder*, OSSIZE *maxOrder*, int *anyID*)

This function parses the next start tag and finds index of element name in descriptor table.

It used for decode "all" content model in strict mode.

Parameters

pctxt Pointer to context block structure.
tab Elements descriptor table.
nrows Number of descriptors in table.
pOrder Pointer to array to receive elements order.
nOrder Last element's index in order array.
maxOrder Size of order array.
anyID Identifier of xsd:any element.

Returns

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

6.4.1.52 int rtXmlpGetNextElem (OSCTXT * *pctxt*, OSXMLElemDescr * *pElem*, OSINT32 *level*)

This function parse the next element start tag.

Parameters

pctxt Pointer to context block structure.
pElem Pointer to a structure to receive the decoded element descriptor.
level Nesting level of parsed start tag. When value equal -1 parsed next start tag.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.53 int rtXmlpGetNextElemID (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, OSSIZE *nrows*, OSINT32 *level*, OSBOOL *continueParse*)

This function parses the next start tag and finds the index of the element name in the descriptor table.

If this reaches the closing tag for the current level, it returns XML_OK_EOB. If this encounters an unexpected element and !continueParse, it returns RTERR_UNEXPELEM (without logging it).

Parameters

pctxt Pointer to context block structure.

tab Elements descriptor table.

nrows Number of descriptors in table.

level Nesting level of parsed start tag. When value equal -1 function parse next start tag.

continueParse When value equals TRUE function skips unrecognized elements; skipped elements are logged, but an error is not returned.

Returns

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

6.4.1.54 int rtXmlpGetNextSeqElemID (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, const OSXMLGroupDesc * *pGroup*, int *curID*, int *lastMandatoryID*, OSBOOL *groupMode*)

This function parses the next start tag and finds index of element name in descriptor table.

It is used to decode sequences in strict mode.

Handling of unexpected elements:

- If the current decode group includes an any case, unexpected elements will be matched against it (the any case id will be returned).
- Otherwise, if groupMode is true, and the element identified by lastMandatoryID has been reached, XML_OK_EOB is returned. The unexpected element may belong to something following the elements in tab.
- If neither of the above applies, unknown elements will be logged and skipped over, with this method continuing as if the unexpected element were not present. Handling of the case of reaching closing tag for current level:
 - If the last mandatory element is reached, return XML_OK_EOB.
 - Otherwise, log and return XML_E_ELEMMSMISRQ.

This function is equivalent to: rtXmlpGetNextSeqElemID2(pctxt, tab, pGroup, curID, lastMandatoryID, groupMode, FALSE);

Parameters

pctxt Pointer to context block structure.
tab Elements descriptor table.
pGroup Decode groups table.
curID Current decode group.
lastMandatoryID Identifier of last mandatory element.
groupMode This parameter must be setted to TRUE when decoding groups or base types.

Returns

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

6.4.1.55 int rtXmlpGetNextSeqElemID2 (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, const OSXMLGroupDesc * *pGroup*, int *groups*, int *curID*, int *lastMandatoryID*, OSBOOL *groupMode*, OSBOOL *checkRepeat*)

This function parses the next start tag and finds index of element name in descriptor table.

It is used to decode sequences in strict mode.

Parameters

pctxt Pointer to context block structure.
tab Elements descriptor table.
pGroup Decode groups table.
groups Number of groups in groups table. If checkRepeat is FALSE, you can pass 0 for this if the value is unknown.
curID Current decode group.
lastMandatoryID Identifier of last mandatory element.
groupMode This parameter must be setted to TRUE when decode groups or base types.
checkRepeat If true, this method is being called to check for a repeat of curID. In this case, we do not treat curID as being required. Otherwise, curID is required if curId <= lastMandatoryID.

Returns

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

6.4.1.56 int rtXmlpGetNextSeqElemIDExt (OSCTXT * *pctxt*, const OSXMLElemIDRec * *tab*, const OSXMLGroupDesc * *ppGroup*, const OSBOOL * *extRequired*, int *postExtRootID*, int *curID*, int *lastMandatoryID*, OSBOOL *groupMode*)

This is an ASN.1 extension-supporting version of rtXmlpGetNextSeqElemID.

It allows required extension elements to be absent, except that when an extension group is present, all required extension elements in that group must be present. It otherwise behaves the same as rtXmlpGetNextSeqElemID.

Parameters

pctxt Pointer to context block structure.

tab Elements descriptor table.

pGroup Decode groups table.

extRequired extRequired[i] corresponds to pGroup[i]. This is TRUE if and only if the decode group ends with a non-optional, non-default extension element that must be present in the encoding (because it is inside an extension group for which some element has already been decoded).

postExtRootID This is the group id corresponding to the decode group that begins with the first root element that follows the extension additions. If there is no such element, this is -1.

curID Current decode group.

lastMandatoryID Identifier of last mandatory element.

groupMode This parameter must be setted to TRUE when decoding groups or base types.

Returns

Completion status of operation:

- positive or zero value is element identifier,
- negative return value is error.

6.4.1.57 struct OSXMLReader* rtXmlpGetReader (OSCTXT * *pctxt*) [read]

This function fetches the XML reader structure from the context for use in low-level pull parser calls.

If the reader structure does not exist, it is created and initialized.

Parameters

pctxt Pointer to context block structure.

Returns

Pointer to XML reader structure or NULL if an error occurred.

6.4.1.58 int rtXmlpGetXmlnsAttrs (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function decodes namespace attributes from start tag and adds them to the given list.

Parameters

pctxt Pointer to context block structure.

pNSAttrs A pointer to a linked list of OSXMLNamespace structures.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.59 int rtXmlpGetXSITypeAttr (OSCTXT * *pctxt*, const OSUTF8CHAR ** *ppAttrValue*, OSINT16 * *nsidx*, OSSIZE * *pLocalOffs*)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).

Parameters

pctxt Pointer to context block structure.

ppAttrValue A pointer to a pointer to a UTF8 character string to received the decoded XSI type QName.

nsidx A pointer to OSINT16 value to received the decoded XSI type namespace index.

pLocalOffs A pointer to size_t value to received the local name offset in ppAttrValue. When pLocalOffs value equal NULL function return in ppAttrValue local name only.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.60 int rtXmlpGetXSITypeIndex (OSCTXT * *pctxt*, const OSXMLItemDescr *typetab*[], OSSIZE *typetabsiz*)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type) and find type index in descriptor table.

Parameters

pctxt Pointer to context block structure.

typetab XSI types descriptor table.

typetabsiz Number of descriptors in table.

Returns

Completion status of operation:

- positive or zero value is type index,
- negative return value is error.

6.4.1.61 OSBOOL rtXmlpHasAttributes (OSCTXT * *pctxt*)

This function checks accessibility of attributes.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- TRUE = attributes are present and access is enabled,
- FALSE = attributes are absent or access is disabled.

6.4.1.62 void rtXmlpHideAttributes (OSCTXT * *pctxt*)

Disable access to attributes.

Function used in derived types to disable repeated decode in base type.

Parameters

pctxt Pointer to context block structure.

6.4.1.63 OSBOOL rtXmlpIsDecodeAsGroup (OSCTXT * *pctxt*)

This function checks if "decode as group" mode was forced.

Parameters

pctxt Pointer to context block structure.

Returns

State of mode:

- TRUE = need decode as group,
- FALSE = normal sequence decoding.

6.4.1.64 OSBOOL rtXmlpIsEmptyElement (OSCTXT * *pctxt*)

Check element content: empty or not.

Parameters

pctxt Pointer to context block structure.

Returns

Status of element content:

- TRUE = element is empty,
- FALSE = element has content.

6.4.1.65 OSBOOL rtXmlpIsLastEventDone (OSCTXT * *pctxt*)

Check processing status of current tag.

Parameters

pctxt Pointer to context block structure.

Returns

Status of element content:

- TRUE = tag marked as processed,
- FALSE = tag will be processed again.

6.4.1.66 OSBOOL rtXmlpIsUTF8Encoding (OSCTXT **pctxt*)

This function checks if the encoding specified in XML header is UTF-8.

Parameters

pctxt Pointer to context block structure.

Returns

State of mode:

- TRUE = is in UTF-8 encoding,
- FALSE = is not in UTF-8 encoding.

6.4.1.67 OSBOOL rtXmlpListHasItem (OSCTXT **pctxt*)

Check for end of decoded token list.

Parameters

pctxt Pointer to context block structure.

Returns

State of decoded list:

- TRUE = list is not finished,
- FALSE = all tokens was decoded.

6.4.1.68 int rtXmlpLookupXSITypeIndex (OSCTXT **pctxt*, const OSUTF8CHAR **pXsiType*, OSINT16 *xsiTypeIdx*, const OSXMLItemDescr *typetab*[], OSSIZE *typetabsiz*)

This function find index of XSI (XML Schema Instance) type in descriptor table.

Parameters

pctxt Pointer to context block structure.

pXsiType A pointer to XSI type name.

xsiTypeIdx A XSI type namespace index.

typetab XSI types descriptor table.

typetabsiz Number of descriptors in table.

Returns

Completion status of operation:

- positive or zero value is type index,
- negative return value is error.

6.4.1.69 int rtXmlpMarkLastEventActive (OSCTXT **pctxt*)

This function marks current tag as unprocessed.

This will cause the element to be processed again in the next pull-parser function.

Parameters

pctxt Pointer to context block structure.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.70 void rtXmlpMarkPos (OSCTXT **pctxt*)

Save current decode position.

Parameters

pctxt Pointer to context block structure.

6.4.1.71 int rtXmlpMatchEndTag (OSCTXT **pctxt*, OSINT32 *level*)

This function parse next end tag that matches with given name.

Parameters

pctxt Pointer to context block structure.

level Nesting level of parsed start tag. When value equal -1 function parse next end tag with current level.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.72 int rtXmlpMatchStartTag (OSCTXT **pctxt*, const OSUTF8CHAR **elemLocalName*, OSINT16 *nsidx*)

This function parses the next start tag that matches with given name.

Parameters

pctxt Pointer to context block structure.

elemLocalName Name of parsed element.

nsidx Namespace index:

- 0 = attribute is unqualified,

- positive value is user namespace from generated namespace table,
- negative value is predefined namespace like XSD instance and ect.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.4.1.73 OSBOOL rtXmlpNeedDecodeAttributes (OSCTXT * *pctxt*)

This function checks if attributes were previously decoded.

Parameters

pctxt Pointer to context block structure.

Returns

State of attributes:

- TRUE = attributes was not decoded,
- FALSE = attributes had been decoded.

6.4.1.74 int rtXmlpReadBytes (OSCTXT * *pctxt*, OSOCTET * *pbuf*, OSSIZE *nbytes*)

This function reads the specified number of bytes directly from the underlying XML parser stream.

It has no effect on any of the parser state variables.

Parameters

pctxt Pointer to context block structure.

pbuf Pointer to static buffer (byte array) to receive data. The buffer must be at least large enough to hold the requested number of bytes.

nbytes Number of bytes to read.

Returns

State of mode:

- TRUE = is in UTF-8 encoding,
- FALSE = is not in UTF-8 encoding.

6.4.1.75 void rtXmlpResetMarkedPos (OSCTXT * *pctxt*)

Reset saved decode position.

Parameters

pctxt Pointer to context block structure.

6.4.1.76 void rtXmlpRewindToMarkedPos (OSCTXT **pctxt*)

Rewind to saved decode position.

Parameters

pctxt Pointer to context block structure.

6.4.1.77 int rtXmlpSelectAttribute (OSCTXT **pctxt*, OSXMLNameFragments **pAttr*, OSINT16 **nsidx*, OSSIZE *attrIndex*)

This function selects attribute to decode.

Parameters

pctxt Pointer to context block structure.

pAttr Pointer to structure to receive the various parts of an attribute name.

nsidx Pointer to value to receive namespace index:

- 0 = attribute is unqualified,
- positive value is user namespace from generated namespace table,
- negative value is predefined namespace like XSD instance and ect (see enum OSXMLNsIndex)

attrIndex Index of selected attribute.

Returns

Completion status of operation:

- positive or zero return value is attribute index in descriptor table,
- negative return value is error.

6.4.1.78 void rtXmlpSetListMode (OSCTXT **pctxt*)

Sets list mode.

Attribute value or element content is decoded by tokens.

Parameters

pctxt Pointer to context block structure.

6.4.1.79 OSBOOL rtXmlpSetMixedContentMode (OSCTXT **pctxt*, OSBOOL *mixedContentMode*)

Sets mixed content mode.

Parameters

pctxt Pointer to context block structure.

mixedContentMode Enable/disable mixed mode.

Returns

Previously state of mixed mode.

6.4.1.80 void rtXmlpSetNamespaceTable (OSCTXT * *pctxt*, const OSUTF8CHAR * *namespaceTable*[], OSSIZE *nmNamespaces*)

Sets user namespace table.

Parameters

pctxt Pointer to context block structure.

namespaceTable Array of namespace URI strings.

nmNamespaces Number of namespaces in table.

6.4.1.81 void rtXmlpSetWhiteSpaceMode (OSCTXT * *pctxt*, OSXMLWhiteSpaceMode *whiteSpaceMode*)

Sets the whitespace treatment mode.

This mode affects the content and attribute values reading. For example, if OSXMLWSM_COLLAPSE mode is set then all spaces in returned data will be already collapsed.

Parameters

pctxt Pointer to context block structure.

whiteSpaceMode White space mode.

Returns

Previously set whitespace mode.

6.5 XML run-time error status codes.

This is a list of status codes that can be returned by XML run-time functions and generated code.

Defines

- `#define XML_OK_EOB 0xffffffff`
End of block marker.
- `#define XML_OK_FRAG XML_OK_EOB`
Maintained for backward compatibility.
- `#define XML_E_BASE -200`
Error base.
- `#define XML_E_GENERR (XML_E_BASE)`
General error.
- `#define XML_E_INVSYMBOL (XML_E_BASE-1)`
An invalid XML symbol (character) was detected at the given point in the parse stream.
- `#define XML_E_TAGMISMATCH (XML_E_BASE-2)`
Start/end tag mismatch.
- `#define XML_E_DUPLATTR (XML_E_BASE-3)`
Duplicate attribute found.
- `#define XML_E_BADCHARREF (XML_E_BASE-4)`
Bad character reference found.
- `#define XML_E_INVMODE (XML_E_BASE-5)`
Invalid mode.
- `#define XML_E_UNEXPEOF (XML_E_BASE-6)`
Unexpected end of file (document).
- `#define XML_E_NOMATCH (XML_E_BASE-7)`
Current tag is not matched to specified one.
- `#define XML_E_ELEMMISRQ (XML_E_BASE-8)`
Missing required element.
- `#define XML_E_ELEMSMISRQ (XML_E_BASE-9)`
Missing required elements.
- `#define XML_E_TOOWEWELEMS (XML_E_BASE-10)`
The number of elements in a repeating collection was less than the number of elements specified in the XSD minOccurs facet for this type or element.
- `#define XML_E_UNEXPSTARTTAG (XML_E_BASE-11)`

Unexpected start tag.

- #define **XML_E_UNEXPENDTAG** (XML_E_BASE-12)

Unexpected end tag.

- #define **XML_E_IDNOTFOU** (XML_E_BASE-13)

Expected identifier not found.

- #define **XML_E_INVTYPEINFO** (XML_E_BASE-14)

Unknown xsi:type.

- #define **XML_E_NSURINOTFOU** (XML_E_BASE-15)

Namespace URI not defined for given prefix.

- #define **XML_E_KEYNOTFOU** (XML_E_BASE-16)

Keyref constraint has some key that not present in refered constraint.

- #define **XML_E_DUPLKEY** (XML_E_BASE-17)

Key or unique constraint has duplicated key.

- #define **XML_E_FLDABSENT** (XML_E_BASE-18)

Some key has no full set of fields.

- #define **XML_E_DUPLFLD** (XML_E_BASE-19)

Some key has more than one value for field.

- #define **XML_E_NOTEEMPTY** (XML_E_BASE-20)

An element was not empty when expected.

6.5.1 Detailed Description

This is a list of status codes that can be returned by XML run-time functions and generated code. In many cases, additional information and parameters for the different errors are stored in the context structure at the time the error is raised. This additional information can be output using the `rtxErrPrint` or `rtxErrLogUsingCB` run-time functions.

6.5.2 Define Documentation

6.5.2.1 #define XML_E_BASE -200

Error base.

XML specific errors start at this base number to distinguish them from common and other error types.

Definition at line 60 of file `rtXmlErrCodes.h`.

6.5.2.2 #define XML_E_ELEMMISRQ (XML_E_BASE-8)

Missing required element.

This status code is returned by the decoder when the decoder knows exactly which element is absent.

Definition at line 121 of file rtXmlErrCodes.h.

6.5.2.3 #define XML_E_ELEMMSMISRQ (XML_E_BASE-9)

Missing required elements.

This status code is returned by the decoder when the number of elements decoded for a given content model group is less than the required number of elements as specified in the schema.

Definition at line 128 of file rtXmlErrCodes.h.

6.5.2.4 #define XML_E_FLDABSENT (XML_E_BASE-18)

Some key has no full set of fields.

It is not valid for key constraint.

Definition at line 199 of file rtXmlErrCodes.h.

6.5.2.5 #define XML_E_NOMATCH (XML_E_BASE-7)

Current tag is not matched to specified one.

Informational code.

Definition at line 115 of file rtXmlErrCodes.h.

6.5.2.6 #define XML_E_NSURINOTFOU (XML_E_BASE-15)

Namespace URI not defined for given prefix.

A namespace URI was not defined using an xmlns attribute for the given prefix.

Definition at line 166 of file rtXmlErrCodes.h.

6.5.2.7 #define XML_E_TAGMISMATCH (XML_E_BASE-2)

Start/end tag mismatch.

The parsed end tag does not match the start tag that was parsed earlier at this level. Indicates document is not well-formed.

Definition at line 90 of file rtXmlErrCodes.h.

6.5.2.8 #define XML_OK_EOB 0x7fffffff

End of block marker.

Definition at line 51 of file rtXmlErrCodes.h.

6.5.2.9 #define XML_OK_FRAG XML_OK_EOB

Maintained for backward compatibility.

Definition at line 54 of file rtXmlErrCodes.h.

6.6 DOM API functions.

Typedefs

- `typedef int OSRTDOMError`
0 - OK <0 - Error code (see rtxsrc/rtxErrCodes.h) >0 - Supplementary code

Functions

- EXTERNDOM void `domParserInit ()`
Inits parser.
- EXTERNDOM void `domParserShutdown ()`
Shutdowns parser.
- EXTERNDOM OSRTDOMError `domParseFile (const char *fileSpec, OSRTDOMDocPtr *pXmlDoc)`
Parse the file into a DOM document.
- EXTERNDOM OSRTDOMError `domGetRootElement (OSRTDOMDocPtr xmlDoc, OSRTDOMNodePtr *pNode)`
Returns root node for the document.
- EXTERNDOM OSRTDOMError `domGetDoc (OSRTDOMNodePtr node, OSRTDOMDocPtr *pXmlDoc)`
Returns the document for the given element.
- EXTERNDOM void `domFreeDoc (OSRTDOMDocPtr xmlDoc)`
Frees document.
- EXTERNDOM OSRTDOMError `domGetNext (const OSRTDOMNodePtr curNode, OSRTDOMNodePtr *pNextNode)`
Returns next element node (down sibling).
- EXTERNDOM OSRTDOMError `domGetChild (const OSRTDOMNodePtr curNode, OSRTDOMNodePtr *pChildNode)`
Returns first (top) child node.
- EXTERNDOM OSRTDOMError `domGetElementName (const OSRTDOMNodePtr curNode, const OS-UTF8CHAR **ppName, const OSUTF8CHAR **ppNsPrefix, const OSUTF8CHAR **ppNsUri)`
Returns node's name and prefix (if any).
- EXTERNDOM int `domGetNodeContent (OSRTDOMContCtxtPtr *ppCtxt, const OSRTDOMNodePtr curNode, const OSUTF8CHAR **ppValue, size_t *pValueLen, OSBOOL *pCdataProcessed)`
Gets the node's content.
- EXTERNDOM OSRTDOMError `domGetNodeFirstAttribute (OSRTDOMAttrCtxtPtr *ppCtxt, const OSRTDOMNodePtr curNode, OSRTDOMAttrPtr *pTopAttrNode)`
Returns the pointer to the first (top) attribute of the node.
- EXTERNDOM int `domGetNodeAttributesNum (const OSRTDOMNodePtr curNode)`

Returns number of attributes in the node.

- EXTERNDOM **OSRTDOMError domGetNextAttr** (OSRTDOMAttrCtxtPtr *ppCtxt, const OSRTDOMAttrPtr curAttrNode, OSRTDOMAttrPtr *pAttrNode)
Returns the next attribute.
- EXTERNDOM **OSRTDOMError domGetAttrData** (const OSRTDOMAttrPtr curAttrNode, const OS-UTF8CHAR **ppAttrName, const OSUTF8CHAR **ppAttrValue, const OSUTF8CHAR **ppAttrPrefix, const OSUTF8CHAR **ppAttrUri)
Returns the attribute's name and value.
- EXTERNDOM **OSRTDOMError domSaveDoc** (OSRTDOMDocPtr xmlDoc, const char *filename)
Saves DOM document to a file.
- EXTERNDOM **OSRTDOMError domCreateDocument** (OSCTXT *pctxt, OSRTDOMDocPtr *pXmlDoc, const OSUTF8CHAR *pNodeName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Creates a new document and a root element.
- EXTERNDOM **OSRTDOMError domCreateChild** (OSCTXT *pctxt, OSRTDOMNodePtr parentNode, const OSUTF8CHAR *pNodeName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSRTDOMNodePtr *pNewNode)
Creates new child node.
- EXTERNDOM **OSRTDOMError domAddAttribute** (OSCTXT *pctxt, OSRTDOMNodePtr node, const OSUTF8CHAR *pAttrName, const OSUTF8CHAR *pAttrValue, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Creates new attribute and adds it to the node.
- EXTERNDOM **OSRTDOMError domAddContent** (OSRTDOMNodePtr node, const OSUTF8CHAR *pContent, size_t contentLen)
Adds content (text) to the node.
- EXTERNDOM **OSRTDOMError domAddCdata** (OSRTDOMNodePtr node, const OSUTF8CHAR *pContent, size_t contentLen)
Adds CDATA section to the node.

6.6.1 Function Documentation

6.6.1.1 EXTERNDOM OSRTDOMError domAddAttribute (OSCTXT *pctxt, OSRTDOMNodePtr node, const OSUTF8CHAR *pAttrName, const OSUTF8CHAR *pAttrValue, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)

Creates new attribute and adds it to the node.

Parameters

pctxt Pointer to context block structure.

node Pointer to the node where attribute to be added.

pAttrName Pointer to the null-terminated string containing name of the attribute.

pAttrValue Pointer to the null-terminated string containing name of the value.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns

0 - success, otherwise error code.

6.6.1.2 EXTERNDOM OSRTDOMError domAddCdata (OSRTDOMNodePtr *node*, const OSUTF8CHAR **pContent*, size_t *contentLen*)

Adds CDATA section to the node.

Parameters

node Pointer to the node where content to be added.

pContent Pointer to UTF-8 encoded content to be wrapped by CDATA section.

contentLen Length of the content

Returns

0 - success, otherwise error code.

6.6.1.3 EXTERNDOM OSRTDOMError domAddContent (OSRTDOMNodePtr *node*, const OSUTF8CHAR **pContent*, size_t *contentLen*)

Adds content (text) to the node.

Parameters

node Pointer to the node where content to be added.

pContent Pointer to UTF-8 encoded content.

contentLen Length of the content

Returns

0 - success, otherwise error code.

6.6.1.4 EXTERNDOM OSRTDOMError domCreateChild (OSCTXT **pctxt*, OSRTDOMNodePtr *parentNode*, const OSUTF8CHAR **pnodeName*, OSXMLNamespace **pNS*, OSRTDList **pNSAttrs*, OSRTDOMNodePtr **pNewNode*)

Creates new child node.

Parameters

pctxt Pointer to context block structure.

parentNode Pointer to the parent node

pnodeName Name of the node

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

pNewNode Pointer to pointer to newly created node.

Returns

0 - success, otherwise error code.

6.6.1.5 EXTERNDOM OSRTDOMError domCreateDocument (OSCTXT * *pctxt*, OSRTDOMDocPtr * *pXmlDoc*, const OSUTF8CHAR * *pnodeName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

Creates a new document and a root element.

Parameters

pctxt Pointer to context block structure.

pXmlDoc Pointer to pointer to the newly created empty DOM document.

pnodeName Name of the node

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns

0 - success, otherwise error code.

6.6.1.6 EXTERNDOM void domFreeDoc (OSRTDOMDocPtr *xmlDoc*)

Frees document.

Parameters

xmlDoc Pointer to the DOM document context

6.6.1.7 EXTERNDOM OSRTDOMError domGetAttrData (const OSRTDOMAttrPtr *curAttrNode*, const OSUTF8CHAR ** *ppAttrName*, const OSUTF8CHAR ** *ppAttrValue*, const OSUTF8CHAR ** *ppAttrPrefix*, const OSUTF8CHAR ** *ppAttrUri*)

Returns the attribute's name and value.

Parameters

curAttrNode Pointer to current attribute node,

ppAttrName Pointer to pointer to receive attribute's name.

ppAttrValue Pointer to pointer to receive attribute's value.

ppAttrPrefix Pointer to pointer to receive namespace's prefix.

ppAttrUri Pointer to pointer to receive namespace's uri.

Returns

0 - success, otherwise error code.

6.6.1.8 EXTERNDOM OSRTDOMError domGetChild (const OSRTDOMNodePtr *curNode*, OSRTDOMNodePtr **pChildNode*)

Returns first (top) child node.

Parameters

curNode Pointer to current node,

pChildNode Pointer to pointer to receive the child node.

Returns

0 - success, otherwise error code.

6.6.1.9 EXTERNDOM OSRTDOMError domGetDoc (OSRTDOMNodePtr *node*, OSRTDOMDocPtr **pXmlDoc*)

Returns the document for the given element.

Parameters

node Pointer to a node.

pXmlDoc Pointer to a pointer to the DOM document context

Returns

0 - success, otherwise error code.

6.6.1.10 EXTERNDOM OSRTDOMError domGetElementName (const OSRTDOMNodePtr *curNode*, const OSUTF8CHAR *ppName*, const OSUTF8CHAR ***ppNsPrefix*, const OSUTF8CHAR ***ppNsUri*)**

Returns node's name and prefix (if any).

Parameters

curNode Pointer to current node,

ppName Pointer to pointer to receive the node's local name.

ppNsPrefix Pointer to pointer to receive the node's prefix. May be NULL, if prefix is not important.

ppNsUri Pointer to pointer to receive the namespace's Uri.

Returns

0 - success, otherwise error code.

6.6.1.11 EXTERNDOM OSRTDOMError domGetNext (const OSRTDOMNodePtr *curNode*, OSRTDOMNodePtr **pNextNode*)

Returns next element node (down sibling).

Parameters

curNode Pointer to current node,
pNextNode Pointer to pointer to receive the next node.

Returns

0 - success, otherwise error code.

6.6.1.12 EXTERNDOM OSRTDOMError domGetNextAttr (OSRTDOMAttrCtxtPtr * *ppCtx*, const OSRTDOMAttrPtr *curAttrNode*, OSRTDOMAttrPtr * *pAttrNode*)

Returns the next attribute.

Parameters

ppCtx Pointer to an implementation-specific context pointer,
curAttrNode Pointer to current attribute node,
pAttrNode Pointer to pointer to receive the next attribute node.

Returns

0 - success, otherwise error code.

6.6.1.13 EXTERNDOM int domGetNodeAttributesNum (const OSRTDOMNodePtr *curNode*)

Returns number of attributes in the node.

Parameters

curNode Pointer to current node,

Returns

Number of attributes in the node.

6.6.1.14 EXTERNDOM int domGetNodeContent (OSRTDOMContCtxtPtr * *ppCtx*, const OSRTDOMNodePtr *curNode*, const OSUTF8CHAR ** *ppValue*, size_t * *pValueLen*, OSBOOL * *pCdataProcessed*)

Gets the node's content.

Parameters

ppCtx Pointer to an implementation-specific content context pointer;
curNode Pointer to the current node;
ppValue Pointer to pointer to receive value;
pValueLen Pointer to value length; may be NULL.
pCdataProcessed Pointer to boolean value; this value will be set to TRUE if CDATA section was proceeded; otherwise FALSE.

Returns

0 - if content retrieved successfully <0 - the error code;

6.6.1.15 EXTERNDOM OSRTDOMError domGetNodeFirstAttribute (OSRTDOMAttrCtxtPtr * *ppCtxt*, const OSRTDOMNodePtr *curNode*, OSRTDOMAttrPtr * *pTopAttrNode*)

Returns the pointer to the first (top) attribute of the node.

The context pointer will be passed to subsequent calls to domGetNextAttr.

Parameters

ppCtxt Pointer to an implementation-specific context pointer,

curNode Pointer to current node,

pTopAttrNode Pointer to pointer to receive the first attribute node. domGetNextAttr/domGetPrevAttr functions may be used to get next/previous attributes.

Returns

0 - success, otherwise error code.

6.6.1.16 EXTERNDOM OSRTDOMError domGetRootElement (OSRTDOMDocPtr *xmlDoc*, OSRTDOMNodePtr * *pNode*)

Returns root node for the document.

Parameters

xmlDoc Pointer to the DOM document context

pNode Pointer to pointer to receive the root node.

Returns

0 - success, otherwise error code.

6.6.1.17 EXTERNDOM OSRTDOMError domParseFile (const char * *fileSpec*, OSRTDOMDocPtr * *pXmlDoc*)

Parse the file into a DOM document.

Parameters

fileSpec File name

pXmlDoc Pointer to a pointer to newly created DOM document.

Returns

0 - success, otherwise error code.

6.6.1.18 EXTERNDOM OSRTDOMError domSaveDoc (OSRTDOMDocPtr *xmlDoc*, const char * *filename*)

Saves DOM document to a file.

This function is supplementary and it is not obligatory to implement it.

Parameters

xmlDoc Pointer to the DOM document context.

filename Pointer to file name.

Returns

0 - success, otherwise error code.

6.7 DOM runtime encode/decode functions.

Functions

- EXTERNDOM int [rtDomAddAttr](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *attrName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)

Adds attribute to the node.
- EXTERNDOM int [rtDomAddNode](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)

Adds child node to the parent's node.
- EXTERNDOM int [rtDomAddNSAttrs](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr rootNode, OSRTDList *pNSAttrs)

Adds namespace attributes to the root node.
- EXTERNDOM int [rtDomEncXSIAttrs](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSBOOL needXSI)

Adds XSI attributes to the node.
- EXTERNDOM int [rtDomDecodeDoc](#) (OSRTDOMDocPtr domDoc, struct OSSAXHandlerBase *pSaxBase)

This function starts decoding of the DOM document.
- EXTERNDOM int [rtDomEncStringValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *pvalue)

This function encodes a variable of the XSD string type.
- EXTERNDOM int [rtDomEncString](#) (OSCTXT *pctxt, OSXMLSTRING *pvalue)

This function encodes a variable of the XSD string type.
- EXTERNDOM int [rtDomEncAny](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSXMLSTRING *pXmlData, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)

This function encodes a variable of the XSD any type.
- EXTERNDOM int [rtDomEncAnyAttr](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSRTDList *pAnyAttrList)

This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- EXTERNDOM int [rtDomSetNode](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr curNode)

Adds content or CDATA section to the node.
- EXTERNDOM int [rtDomAddSubTree](#) (OSCTXT *pctxt, OSRTDOMDocPtr xmlDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *pXmlData, size_t dataLen)

This function adds the subtree to the specified node.

6.7.1 Function Documentation

6.7.1.1 EXTERNDOM int rtDomAddAttr (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *node*, const OSUTF8CHAR * *attrName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

Adds attribute to the node.

The value is taken from the context's buffer (*pctxt*->buffer.data with the length *pctxt*->buffer.byteIndex). This function resets *pctxt*->buffer.byteIndex to 0.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

node A pointer to a node where attribute to be added.

attrName A pointer to attribute's name.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.2 EXTERNDOM int rtDomAddNode (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *parentNode*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

Adds child node to the parent's node.

The content (text) is taken from the context's buffer (*pctxt*->buffer.data with the length *pctxt*->buffer.byteIndex). If *pctxt*->buffer.byteIndex is 0 then empty element is added. This function resets *pctxt*->buffer.byteIndex to 0.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

parentNode A pointer to a parent node.

elemName A pointer to element's name.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.3 EXTERNDOM int rtDomAddNSAttrs (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *rootNode*, OSRTDList * *pNSAttrs*)

Adds namespace attributes to the root node.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

rootNode A pointer to a root node.

pNSAttrs A pointer to a list of namespace attrs.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.4 EXTERNDOM int rtDomAddSubTree (OSCTXT * *pctxt*, OSRTDOMDocPtr *xmlDoc*, OSRTDOMNodePtr *node*, const OSUTF8CHAR * *pXmlData*, size_t *dataLen*)

This function adds the subtree to the specified node.

The *pXmlData* contains the fragment of XML data. This fragment is parsed to sub-tree and then inserted as children to the '*node*'.

Parameters

pctxt Pointer to the context structure. This context might be used for memory allocations, if necessary.

xmlDoc Pointer to the document

node Pointer to the node where sub-tree to be inserted.

pXmlData Pointer to UTF-8 string representing fragment of XML data. For example, "<elem>data</elem>".

dataLen Length of XML data.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.5 EXTERNDOM int rtDomDecodeDoc (OSRTDOMDocPtr *domDoc*, struct OSSAXHandlerBase * *pSaxBase*)

This function starts decoding of the DOM document.

Parameters

domDoc A pointer to a DOM-document.

pSaxBase A pointer to SAX handler's base.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.6 EXTERNDOM int rtDomEncAny (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *parentNode*, const OSXMLSTRING * *pXmlData*, const OSUTF8CHAR * *elemName*, OSXMLNamespace * *pNS*, OSRTDList * *pNSAttrs*)

This function encodes a variable of the XSD any type.

This is considered to be a fully-wrapped element of any type (for example: <myType>myData</myType>)

Parameters

pctxt Pointer to context block structure.

domDoc A pointer to a DOM-document.

parentNode A pointer to a parent node.

pXmlData Value to be encoded. This is a string containing the fully-encoded XML text to be copied to the output stream.

elemName XML element name. A name must be provided. If NULL pointer is passed, no element tag is added to the encoded value.

pNS XML namespace information (prefix and URI).

pNSAttrs List of namespace attributes to be added to element.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.7 EXTERNDOM int rtDomEncAnyAttr (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *node*, OSRTDList * *pAnyAttrList*)

This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.

Parameters

pctxt Pointer to context block structure.

domDoc A pointer to a DOM-document.

node A pointer to a node where attributes to be added.

pAnyAttrList List of attributes.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.8 EXTERNDOM int rtDomEncString (OSCTXT * *pctxt*, OSXMLSTRING * *pvalue*)

This function encodes a variable of the XSD string type.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* XML string value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.9 EXTERNDOM int rtDomEncStringValue (OSCTXT * *pctxt*, const OSUTF8CHAR * *pvalue*)

This function encodes a variable of the XSD string type.

Parameters

- pctxt* Pointer to context block structure.
- pvalue* Null-terminated XML string value to be encoded.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.10 EXTERNDOM int rtDomEncXSIAttrs (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *node*, OSBOOL *needXSI*)

Adds XSI attributes to the node.

Parameters

- pctxt* A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.
- domDoc* A pointer to a DOM-document.
- node* A pointer to a node.
- needXSI* Determines whether XSI namespace declaration needed.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

6.7.1.11 EXTERNDOM int rtDomSetNode (OSCTXT * *pctxt*, OSRTDOMDocPtr *domDoc*, OSRTDOMNodePtr *curNode*)

Adds content or CDATA section to the node.

The content (text) is taken from the context's buffer (*pctxt*->buffer.data with the length *pctxt*->buffer.byteIndex). This function resets *pctxt*->buffer.byteIndex to 0.

Parameters

pctxt A pointer to a context structure. This provides a storage area for the function to store all working variables that must be maintained between function calls.

domDoc A pointer to a DOM-document.

curNode A pointer to a current node.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

Chapter 7

Class Documentation

7.1 OSXMLGroupDesc Struct Reference

[OSXMLGroupDesc](#) describes how entries in an OSXMLElemIDRec array make up a group.

```
#include <osrtxml.h>
```

7.1.1 Detailed Description

[OSXMLGroupDesc](#) describes how entries in an OSXMLElemIDRec array make up a group. Here, "group" means a set of elements, any of which may be matched next. This does not correspond directly to an XSD group.

For example, if elementA is optional and followed by non-optional elementB, then there will be a group that contains both elements. There will also be a group that contains only elementB; this will be the group of interest after elementA is matched.

Definition at line 142 of file osrtxml.h.

The documentation for this struct was generated from the following file:

- [osrtxml.h](#)

Chapter 8

File Documentation

8.1 osrtdom.h File Reference

DOM low-level C encode/decode functions.

```
#include "rtxsrc/rtxCommon.h"
#include "rtdomsrc/rtxDomDefs.h"
#include "rtxmlsrc/osrtxml.h"
#include "rtdomsrc/domAPI.h"
#include "rtxmlsrc/rtXmlNamespace.h"
```

Functions

- EXTERNDOM int [rtDomAddAttr](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *attrName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Adds attribute to the node.
- EXTERNDOM int [rtDomAddNode](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
Adds child node to the parent's node.
- EXTERNDOM int [rtDomAddNSAttrs](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr rootNode, OSRTDList *pNSAttrs)
Adds namespace attributes to the root node.
- EXTERNDOM int [rtDomEncXSIAttrs](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSBOOL needXSI)
Adds XSI attributes to the node.
- EXTERNDOM int [rtDomDecodeDoc](#) (OSRTDOMDocPtr domDoc, struct OSSAXHandlerBase *pSaxBase)
This function starts decoding of the DOM document.
- EXTERNDOM int [rtDomEncStringValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *pvalue)
This function encodes a variable of the XSD string type.

- EXTERNDOM int [rtDomEncString](#) (OSCTXT *pctxt, OSXMLSTRING *pvalue)
This function encodes a variable of the XSD string type.
- EXTERNDOM int [rtDomEncAny](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr parentNode, const OSXMLSTRING *pXmlData, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs)
This function encodes a variable of the XSD any type.
- EXTERNDOM int [rtDomEncAnyAttr](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr node, OSRTDList *pAnyAttrList)
This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- EXTERNDOM int [rtDomSetNode](#) (OSCTXT *pctxt, OSRTDOMDocPtr domDoc, OSRTDOMNodePtr curNode)
Adds content or CDATA section to the node.
- EXTERNDOM int [rtDomAddSubTree](#) (OSCTXT *pctxt, OSRTDOMDocPtr xmlDoc, OSRTDOMNodePtr node, const OSUTF8CHAR *pXmlData, size_t dataLen)
This function adds the subtree to the specified node.

8.1.1 Detailed Description

DOM low-level C encode/decode functions.

Definition in file [osrtdom.h](#).

8.2 osrtxml.h File Reference

XML low-level C encode/decode functions.

```
#include "rtxsrc/rtxCommon.h"
#include "rtxmlsrc/rtSaxDefs.h"
#include "rtxsrc/rtxDList.h"
#include "rtxsrc/rtxMemBuf.h"
#include "rtxmlsrc/rtXmlExternDefs.h"
#include "rtxmlsrc/rtXmlErrCodes.h"
#include "rtxmlsrc/rtXmlNamespace.h"
```

Classes

- struct [OSXMLGroupDesc](#)

OSXMLGroupDesc describes how entries in an OSXMLElemIDRec array make up a group.

Defines

- #define [rtXmlGetEncBufPtr](#)(pctxt) (pctxt)->buffer.data
This macro returns the start address of the encoded XML message.
- #define [rtXmlGetEncBufLen](#)(pctxt) (pctxt)->buffer.byteIndex
This macro returns the length of the encoded XML message.

Typedefs

- typedef struct [OSXMLGroupDesc](#) [OSXMLGroupDesc](#)
OSXMLGroupDesc describes how entries in an OSXMLElemIDRec array make up a group.

Enumerations

- enum [OSXMLWhiteSpaceMode](#)
Whitespace treatment options.

Functions

- int [rtXmlInitContext](#) (OSCTXT *pctxt)
This function initializes a context variable for XML encoding or decoding.
- int [rtXmlInitContextUsingKey](#) (OSCTXT *pctxt, const OSOCTET *key, OSSIZE keylen)
This function initializes a context using a run-time key.

- int **rtXmlInitCtxtAppInfo** (OSCTXT *pctxt)

This function initializes the XML application info section of the given context.
- int **rtXmlCreateFileInputSource** (OSCTXT *pctxt, const char *filepath)

This function creates an XML document file input source.
- void **rtXmlMemFreeAnyAttrs** (OSCTXT *pctxt, OSRTDList *pAnyAttrList)

This function frees a list of anyAttribute that is a member of OSXSDAnyType structure.
- int **rtXmlDecBase64Binary** (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, OSSIZE length)

This function decodes the contents of a Base64-encoded binary data type into a memory buffer.
- int **rtXmlDecBase64Str** (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)

This function decodes a contents of a Base64-encode binary string into a static memory structure.
- int **rtXmlDecBase64StrValue** (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSSIZE bufSize, OSSIZE srcDataLen)

This function decodes a contents of a Base64-encode binary string into the specified octet array.
- int **rtXmlDecBigInt** (OSCTXT *pctxt, const OSUTF8CHAR **ppvalue)

This function will decode a variable of the XSD integer type.
- int **rtXmlDecBool** (OSCTXT *pctxt, OSBOOL *pvalue)

This function decodes a variable of the boolean type.
- int **rtXmlDecDate** (OSCTXT *pctxt, OSXSDDateTime *pvalue)

This function decodes a variable of the XSD 'date' type.
- int **rtXmlDecTime** (OSCTXT *pctxt, OSXSDDateTime *pvalue)

This function decodes a variable of the XSD 'time' type.
- int **rtXmlDecDateTime** (OSCTXT *pctxt, OSXSDDateTime *pvalue)

This function decodes a variable of the XSD 'dateTime' type.
- int **rtXmlDecDecimal** (OSCTXT *pctxt, OSREAL *pvalue)

This function decodes the contents of a decimal data type.
- int **rtXmlDecDouble** (OSCTXT *pctxt, OSREAL *pvalue)

This function decodes the contents of a float or double data type.
- int **rtXmlDecDynBase64Str** (OSCTXT *pctxt, OSDynOctStr *pvalue)

This function decodes a contents of a Base64-encode binary string.
- int **rtXmlDecDynHexStr** (OSCTXT *pctxt, OSDynOctStr *pvalue)

This function decodes a contents of a hexBinary string.
- int **rtXmlDecEmptyElement** (OSCTXT *pctxt)

This function is used to enforce a requirement that an element be empty.

- int [rtXmlDecUTF8Str](#) (OSCTXT *pctxt, OSUTF8CHAR *outdata, OSSIZE max_len)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecDynUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR **outdata)
This function decodes the contents of a UTF-8 string data type.
- int [rtXmlDecHexBinary](#) (OSRTMEMBUF *pMemBuf, const OSUTF8CHAR *inpdata, OSSIZE length)
This function decodes the contents of a hex-encoded binary data type into a memory buffer.
- int [rtXmlDecHexStr](#) (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int [rtXmlDecGYear](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int [rtXmlDecGYearMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int [rtXmlDecGMonth](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonth' type.
- int [rtXmlDecGMonthDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonthDay' type.
- int [rtXmlDecGDay](#) (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gDay' type.
- int [rtXmlDecInt](#) (OSCTXT *pctxt, OSINT32 *pvalue)
This function decodes the contents of a 32-bit integer data type.
- int [rtXmlDecInt8](#) (OSCTXT *pctxt, OSINT8 *pvalue)
This function decodes the contents of an 8-bit integer data type (i.e.
- int [rtXmlDecInt16](#) (OSCTXT *pctxt, OSINT16 *pvalue)
This function decodes the contents of a 16-bit integer data type.
- int [rtXmlDecInt64](#) (OSCTXT *pctxt, OSINT64 *pvalue)
This function decodes the contents of a 64-bit integer data type.
- int [rtXmlDecUInt](#) (OSCTXT *pctxt, OSUINT32 *pvalue)
This function decodes the contents of an unsigned 32-bit integer data type.
- int [rtXmlDecUInt8](#) (OSCTXT *pctxt, OSUINT8 *pvalue)
This function decodes the contents of an unsigned 8-bit integer data type (i.e.
- int [rtXmlDecUInt16](#) (OSCTXT *pctxt, OSUINT16 *pvalue)
This function decodes the contents of an unsigned 16-bit integer data type.
- int [rtXmlDecUInt64](#) (OSCTXT *pctxt, OSUINT64 *pvalue)
This function decodes the contents of an unsigned 64-bit integer data type.

- int **rtXmlDecNSAttr** (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue, OSRTDList *pNSAttrs, const OSUTF8CHAR *nsTable[], OSUINT32 nsTableRowCount)

This function decodes an XML namespace attribute (xmlns).
- const OSUTF8CHAR * **rtXmlDecQName** (OSCTXT *pctxt, const OSUTF8CHAR *qname, const OSUTF8CHAR **prefix)

This function decodes an XML qualified name string (QName) type.
- int **rtXmlDecXSIAttr** (OSCTXT *pctxt, const OSUTF8CHAR *attrName, const OSUTF8CHAR *attrValue)

This function decodes XML schema instance (XSI) attribute.
- int **rtXmlDecXSIAttrs** (OSCTXT *pctxt, const OSUTF8CHAR *const *attrs, const char *typeName)

This function decodes XML schema instance (XSI) attributes.
- int **rtXmlDecXmlStr** (OSCTXT *pctxt, OSXMLSTRING *outdata)

This function decodes the contents of an XML string data type.
- int **rtXmlParseElementName** (OSCTXT *pctxt, OSUTF8CHAR **ppName)

This function parses the initial tag from an XML message.
- int **rtXmlParseElem QName** (OSCTXT *pctxt, OSXMLQName *pQName)

This function parses the initial tag from an XML message.
- int **rtXmlEncAny** (OSCTXT *pctxt, OSXMLSTRING *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD any type.
- int **rtXmlEncAnyTypeValue** (OSCTXT *pctxt, const OSUTF8CHAR *pvalue)

This function encodes a variable of the XSD anyType type.
- int **rtXmlEncAnyAttr** (OSCTXT *pctxt, OSRTDList *pAnyAttrList)

This function encodes a list of OSAnyAttr attributes in which the name and value are given as a UTF-8 string.
- int **rtXmlEncBase64Binary** (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD base64Binary type.
- int **rtXmlEncBase64BinaryAttr** (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD base64Binary type as an attribute.
- int **rtXmlEncBase64StrValue** (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value)

This function encodes a variable of the XSD base64Binary type.
- int **rtXmlEncBigInt** (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD integer type.
- int **rtXmlEncBigIntAttr** (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD integer type.

This function encodes an XSD integer attribute value.

- int **rtXmlEncBigIntValue** (OSCTXT *pctxt, const OSUTF8CHAR *value)
This function encodes an XSD integer attribute value.
- int **rtXmlEncBitString** (OSCTXT *pctxt, OSUINT32 nbits, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the ASN.1 BIT STRING type.
- int **rtXmlEncBinStrValue** (OSCTXT *pctxt, OSUINT32 nbits, const OSOCTET *data)
This function encodes a binary string value as a sequence of '1's and '0's.
- int **rtXmlEncBool** (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD boolean type.
- int **rtXmlEncBoolValue** (OSCTXT *pctxt, OSBOOL value)
This function encodes a variable of the XSD boolean type.
- int **rtXmlEncBoolAttr** (OSCTXT *pctxt, OSBOOL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)
This function encodes an XSD boolean attribute value.
- int **rtXmlEncComment** (OSCTXT *pctxt, const OSUTF8CHAR *comment)
This function encodes an XML comment.
- int **rtXmlEncDate** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD 'date' type as a string.
- int **rtXmlEncDateValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)
This function encodes a variable of the XSD 'date' type as a string.
- int **rtXmlEncTime** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD 'time' type as a string.
- int **rtXmlEncTimeValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)
This function encodes a variable of the XSD 'time' type as a string.
- int **rtXmlEncDateTime** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a numeric date/time value into an XML string representation.
- int **rtXmlEncDateTimeValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)
This function encodes a numeric date/time value into an XML string representation.
- int **rtXmlEncDecimal** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDecimalFmt *pFmtSpec)
This function encodes a variable of the XSD decimal type.

- int **rtXmlEncDecimalAttr** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen, const OSDecimalFmt *pFmtSpec)

This function encodes a variable of the XSD decimal type as an attribute.
- int **rtXmlEncDecimalValue** (OSCTXT *pctxt, OSREAL value, const OSDecimalFmt *pFmtSpec, char *pDestBuf, OSSIZE destBufSize)

This function encodes a value of the XSD decimal type.
- int **rtXmlEncDouble** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD double type.
- int **rtXmlEncDoubleAttr** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD double type as an attribute.
- int **rtXmlEncDoubleNormalValue** (OSCTXT *pctxt, OSREAL value, const OSDoubleFmt *pFmtSpec, int defaultPrecision)

This function encodes a normal (not +/-INF or NaN) value of the XSD double or float type.
- int **rtXmlEncdoubleValue** (OSCTXT *pctxt, OSREAL value, const OSDoubleFmt *pFmtSpec, int defaultPrecision)

This function encodes a value of the XSD double or float type.
- int **rtXmlEncEmptyElement** (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)

This function encodes an empty element tag value (<elemName/>).
- int **rtXmlEncEndDocument** (OSCTXT *pctxt)

This function adds trailer information and a null terminator at the end of the XML document being encoded.
- int **rtXmlEncEndElement** (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes an end element tag value (</elemName>).
- int **rtXmlEncEndSoapEnv** (OSCTXT *pctxt)

This function encodes a SOAP envelope end element tag (<SOAP-ENV:Envelope/>).
- int **rtXmlEncEndSoapElems** (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)

This function encodes SOAP end element tags.
- int **rtXmlEncFloat** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD float type.
- int **rtXmlEncFloatAttr** (OSCTXT *pctxt, OSREAL value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen, const OSDoubleFmt *pFmtSpec)

This function encodes a variable of the XSD float type as an attribute.
- int **rtXmlEncGYear** (OSCTXT *pctxt, const OSXSDDateType *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gYear element into an XML string representation.

- int **rtXmlEncGYearMonth** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gYearMonth element into an XML string representation.
- int **rtXmlEncGMonth** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gMonth element into an XML string representation.
- int **rtXmlEncGMonthDay** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gMonthDay element into an XML string representation.
- int **rtXmlEncGDay** (OSCTXT *pctxt, const OSXSDDate *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a numeric gDay element into an XML string representation.
- int **rtXmlEncGYearValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gYear value into an XML string representation.
- int **rtXmlEncGYearMonthValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gYearMonth value into an XML string representation.
- int **rtXmlEncGMonthValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gMonth value into an XML string representation.
- int **rtXmlEncGMonthDayValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gMonthDay value into an XML string representation.
- int **rtXmlEncGDayValue** (OSCTXT *pctxt, const OSXSDDate *pvalue)

This function encodes a numeric gDay value into an XML string representation.
- int **rtXmlEncHexBinary** (OSCTXT *pctxt, OSSIZE nocts, const OSOCTET *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD hexBinary type.
- int **rtXmlEncHexBinaryAttr** (OSCTXT *pctxt, OSUINT32 nocts, const OSOCTET *value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD hexBinary type as an attribute.
- int **rtXmlEncHexStrValue** (OSCTXT *pctxt, OSSIZE nocts, const OSOCTET *data)

This function encodes a variable of the XSD hexBinary type.
- int **rtXmlEncIndent** (OSCTXT *pctxt)

This function adds indentation whitespace to the output stream.
- int **rtXmlEncInt** (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD integer type.
- int **rtXmlEncIntValue** (OSCTXT *pctxt, OSINT32 value)

This function encodes a variable of the XSD integer type.

- int **rtXmlEncIntAttr** (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD integer type as an attribute (name="value").

- int **rtXmlEncIntPattern** (OSCTXT *pctxt, OSINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, const OSUTF8CHAR *pattern)

This function encodes a variable of the XSD integer type using a pattern to specify the format of the integer value.

- int **rtXmlEncInt64** (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the XSD integer type.

- int **rtXmlEncInt64Value** (OSCTXT *pctxt, OSINT64 value)

This function encodes a variable of the XSD integer type.

- int **rtXmlEncInt64Attr** (OSCTXT *pctxt, OSINT64 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD integer type as an attribute (name="value").

- int **rtXmlEncNamedBits** (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSUINT32 nbits, const OSOCTET *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the ASN.1 BIT STRING type.

- int **rtXmlEncNSAttrs** (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function encodes namespace declaration attributes at the beginning of an XML document.

- int **rtXmlPrintNSAttrs** (const char *name, const OSRTDList *data)

This function prints a list of namespace attributes.

- int **rtXmlEncReal10** (OSCTXT *pctxt, const OSUTF8CHAR *pvalue, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)

This function encodes a variable of the ASN.1 REAL base 10 type.

- int **rtXmlEncSoapArrayTypeAttr** (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value, OSSIZE itemCount)

This function encodes the special SOAP encoding attrType attribute which specifies the number and type of elements in a SOAP array.

- int **rtXmlEncStartDocument** (OSCTXT *pctxt)

This function encodes the XML header text at the beginning of an XML document.

- int **rtXmlEncBOM** (OSCTXT *pctxt)

This function encodes the Unicode byte order mark header at the start of the document.

- int **rtXmlEncStartElement** (OSCTXT *pctxt, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS, OSRTDList *pNSAttrs, OSBOOL terminate)

This function encodes a start element tag value (<elemName>).

- int **rtXmlEncStartSoapEnv** (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function encodes a SOAP envelope start element tag.

- int [rtXmlEncStartSoapElems](#) (OSCTXT *pctxt, OSXMLSOAPMsgType msgtype)
This function encodes a SOAP envelope start element tag and an optional SOAP body or fault tag.
- int [rtXmlEncString](#) (OSCTXT *pctxt, OSXMLSTRING *pxmlstr, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD string type.
- int [rtXmlEncStringValue](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)
This function encodes a variable of the XSD string type.
- int [rtXmlEncStringValue2](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, OSSIZE valueLen)
This function encodes a variable of the XSD string type.
- int [rtXmlEncTermStartElement](#) (OSCTXT *pctxt)
This function terminates a currently open XML start element by adding either a '>' or '/>' (if empty) terminator.
- int [rtXmlEncUnicodeStr](#) (OSCTXT *pctxt, const OSUNICHAR *value, OSSIZE nchars, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a Unicode string value.
- int [rtXmlEncUTF8Attr](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, const OSUTF8CHAR *value)
This function encodes an attribute in which the name and value are given as a null-terminated UTF-8 strings.
- int [rtXmlEncUTF8Attr2](#) (OSCTXT *pctxt, const OSUTF8CHAR *name, OSSIZE nameLen, const OSUTF8CHAR *value, OSSIZE valueLen)
This function encodes an attribute in which the name and value are given as a UTF-8 strings with lengths.
- int [rtXmlEncUTF8Str](#) (OSCTXT *pctxt, const OSUTF8CHAR *value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a UTF-8 string value.
- int [rtXmlEncUInt](#) (OSCTXT *pctxt, OSUINT32 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD unsigned integer type.
- int [rtXmlEncUIntValue](#) (OSCTXT *pctxt, OSUINT32 value)
This function encodes a variable of the XSD unsigned integer type.
- int [rtXmlEncUIntAttr](#) (OSCTXT *pctxt, OSUINT32 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)
This function encodes a variable of the XSD unsigned integer type as an attribute (name="value").
- int [rtXmlEncUInt64](#) (OSCTXT *pctxt, OSUINT64 value, const OSUTF8CHAR *elemName, OSXMLNamespace *pNS)
This function encodes a variable of the XSD integer type.
- int [rtXmlEncUInt64Value](#) (OSCTXT *pctxt, OSUINT64 value)
This function encodes a variable of the XSD integer type.

- int [rtXmlEncUInt64Attr](#) (OSCTXT *pctxt, OSUINT64 value, const OSUTF8CHAR *attrName, OSSIZE attrNameLen)

This function encodes a variable of the XSD integer type as an attribute (name="value").
- int [rtXmlEncXSIAttrs](#) (OSCTXT *pctxt, OSBOOL needXSI)

This function encodes XML schema instance (XSI) attributes at the beginning of an XML document.
- int [rtXmlEncXSITypeAttr](#) (OSCTXT *pctxt, const OSUTF8CHAR *value)

This function encodes an XML schema instance (XSI) type attribute value (xsi:type="value").
- int [rtXmlEncXSITypeAttr2](#) (OSCTXT *pctxt, const OSUTF8CHAR *typeNsUri, const OSUTF8CHAR *typeName)

This function encodes an XML schema instance (XSI) type attribute value (xsi:type="pfx:value").
- int [rtXmlEncXSINilAttr](#) (OSCTXT *pctxt)

This function encodes an XML nil attribute (xsi:nil="true").
- int [rtXmlFreeInputSource](#) (OSCTXT *pctxt)

This function closes an input source that was previously created with one of the create input source functions such as 'rtXmlCreateFileInputSource'.
- int [rtXmlSetEncBufPtr](#) (OSCTXT *pctxt, OSOCTET *bufaddr, OSSIZE bufsiz)

This function is used to set the internal buffer within the run-time library encoding context.
- int [rtXmlGetIndent](#) (OSCTXT *pctxt)

This function returns current XML output indent value.
- OSBOOL [rtXmlGetWriteBOM](#) (OSCTXT *pctxt)

This function returns whether the Unicode byte order mark will be encoded.
- int [rtXmlGetIndentChar](#) (OSCTXT *pctxt)

This function returns current XML output indent character value (default is space).
- int [rtXmlPrepareContext](#) (OSCTXT *pctxt)

This function prepares the context for another encode by setting the state back to OSXMLINIT and moving the buffer's cursor back to the beginning of the buffer.
- int [rtXmlSetEncC14N](#) (OSCTXT *pctxt, OSBOOL value)

This function sets the option to encode in C14N mode.
- int [rtXmlSetEncXSINamespace](#) (OSCTXT *pctxt, OSBOOL value)

This function sets a flag in the context that indicates the XSI namespace declaration (xmlns:xsi) should be added to the encoded XML instance.
- int [rtXmlSetEncXSINilAttr](#) (OSCTXT *pctxt, OSBOOL value)

This function sets a flag in the context that indicates the XSI attribute declaration (xmlns:xsi) should be added to the encoded XML instance.
- int [rtXmlSetEncDocHdr](#) (OSCTXT *pctxt, OSBOOL value)

This function sets the option to add the XML document header (i.e.

- int **rtXmlSetEncodingStr** (OSCTXT *pctxt, const OSUTF8CHAR *encodingStr)
This function sets the XML output encoding to the given value.
- int **rtXmlSetFormatting** (OSCTXT *pctxt, OSBOOL doFormatting)
This function sets XML output formatting to the given value.
- int **rtXmlSetIndent** (OSCTXT *pctxt, OSUINT8 indent)
This function sets XML output indent to the given value.
- int **rtXmlSetIndentChar** (OSCTXT *pctxt, char indentChar)
This function sets XML output indent character to the given value.
- void **rtXmlSetNamespacesSet** (OSCTXT *pctxt, OSBOOL value)
This function sets the context 'namespaces are set' flag.
- int **rtXmlSetNSPrefixLinks** (OSCTXT *pctxt, OSRTDList *pNSAttrs)
This function sets namespace prefix/URI links in the namespace prefix stack in the context structure.
- int **rtXmlSetSchemaLocation** (OSCTXT *pctxt, const OSUTF8CHAR *schemaLocation)
This function sets the XML Schema Instance (xsi) schema location attribute to be added to an encoded document.
- int **rtXmlSetNoNSSchemaLocation** (OSCTXT *pctxt, const OSUTF8CHAR *schemaLocation)
This function sets the XML Schema Instance (xsi) no namespace schema location attribute to be added to an encoded document.
- void **rtXmlSetSoapVersion** (OSCTXT *pctxt, OSUINT8 version)
This function sets the SOAP version number.
- int **rtXmlSetXSITypeAttr** (OSCTXT *pctxt, const OSUTF8CHAR *xsiType)
This function sets the XML Schema Instance (xsi) type attribute value.
- int **rtXmlSetWriteBOM** (OSCTXT *pctxt, OSBOOL write)
This function sets whether the Unicode byte order mark is encoded.
- int **rtXmlMatchHexStr** (OSCTXT *pctxt, OSSIZE minLength, OSSIZE maxLength)
This function tests the context buffer for containing a correct hexadecimal string.
- int **rtXmlMatchBase64Str** (OSCTXT *pctxt, OSSIZE minLength, OSSIZE maxLength)
This function tests the context buffer for containing a correct base64 string.
- int **rtXmlMatchDate** (OSCTXT *pctxt)
This function tests the context buffer for containing a correct date string.
- int **rtXmlMatchTime** (OSCTXT *pctxt)
This function tests the context buffer for containing a correct time string.
- int **rtXmlMatchDateTime** (OSCTXT *pctxt)
This function tests the context buffer for containing a correct dateTime string.
- int **rtXmlMatchGYear** (OSCTXT *pctxt)

This function tests the context buffer for containing a correct gYear string.

- int **rtXmlMatchGYearMonth** (OSCTXT *pctxt)

This function tests the context buffer for containing a correct gYearMonth string.

- int **rtXmlMatchGMonth** (OSCTXT *pctxt)

This function tests the context buffer for containing a correct gMonth string.

- int **rtXmlMatchGMonthDay** (OSCTXT *pctxt)

This function tests the context buffer for containing a correct gMonthDay string.

- int **rtXmlMatchGDay** (OSCTXT *pctxt)

This function tests the context buffer for containing a correct gDay string.

- OSUTF8CHAR * **rtXmlNewQName** (OSCTXT *pctxt, const OSUTF8CHAR *localName, const OSUTF8CHAR *prefix)

This function creates a new QName given the localName and prefix parts.

- OSBOOL **rtXmlCmpBase64Str** (OSUINT32 nocts1, const OSOCTET *data1, const OSUTF8CHAR *data2)

This function compares an array of octets to a base64 string.

- OSBOOL **rtXmlCmpHexStr** (OSUINT32 nocts1, const OSOCTET *data1, const OSUTF8CHAR *data2)

This function compares an array of octets to a hex string.

- const OSUTF8CHAR * **rtSaxGetAttrValue** (const OSUTF8CHAR *attrName, const OSUTF8CHAR *const *attrs)

This function looks up an attribute in the attribute array returned by SAX to the startElement function.

- OSINT16 **rtSaxGetElemID** (OSINT16 *pState, OSINT16 prevElemIdx, const OSUTF8CHAR *localName, OSINT32 nsidx, const OSSAXElemTableRec idtab[], const OSINT16 *fstab, OSINT16 fstabRows, OSINT16 fstabCols)

This function looks up a sequence element name in the given element info array.

- OSINT16 **rtSaxGetElemID8** (OSINT16 *pState, OSINT16 prevElemIdx, const OSUTF8CHAR *localName, OSINT32 nsidx, const OSSAXElemTableRec idtab[], const OSINT8 *fstab, OSINT16 fstabRows, OSINT16 fstabCols)

This function is a space optimized version of rtSaxGetElemID.

- OSBOOL **rtSaxHasXMLNSAttrs** (const OSUTF8CHAR *const *attrs)

This function checks if the given attribute list contains one or more XML namespace attributes (xmlns).

- OSBOOL **rtSaxIsEmptyBuffer** (OSCTXT *pctxt)

This function checks if the buffer in the context is empty or not.

- int **rtSaxStrListParse** (OSCTXT *pctxt, OSRTMEMBUF *pMemBuf, OSRTDList *pvalue)

This function parses the list of strings.

- int **rtSaxSortAttrs** (OSCTXT *pctxt, const OSUTF8CHAR *const *attrs, OSUINT16 **order)

This function sorts a SAX attribute list in ascending order based on attribute name.

- int **rtSaxStrListMatch** (OSCTXT *pctxt)

This function matches the list of strings.

- int **rtXmlWriteToFile** (OSCTXT *pctxt, const char *filename)
This function writes the encoded XML message stored in the context message buffer out to a file.
- int **rtXmlpDecAny** (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int **rtXmlpDecAny2** (OSCTXT *pctxt, OSUTF8CHAR **pvalue)
This version of the rtXmlpDecAny function returns the string in a mutable buffer.
- int **rtXmlpDecAnyAttrStr** (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrStr, OSSIZE attrIndex)
This function decodes an any attribute string.
- int **rtXmlpDecAnyElem** (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function decodes an arbitrary XML section of code as defined by the XSD any type (xsd:any).
- int **rtXmlpDecBase64Str** (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocnts, OSSIZE bufsize)
This function decodes a contents of a Base64-encode binary string into a static memory structure.
- int **rtXmlpDecBigInt** (OSCTXT *pctxt, const OSUTF8CHAR **pvalue)
This function will decode a variable of the XSD integer type.
- int **rtXmlpDecBitString** (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes a bit string value.
- int **rtXmlpDecBool** (OSCTXT *pctxt, OSBOOL *pvalue)
This function decodes a variable of the boolean type.
- int **rtXmlpDecDate** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'date' type.
- int **rtXmlpDecDateTime** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'dateTime' type.
- int **rtXmlpDecDecimal** (OSCTXT *pctxt, OSREAL *pvalue, int totalDigits, int fractionDigits)
This function decodes the contents of a decimal data type.
- int **rtXmlpDecDouble** (OSCTXT *pctxt, OSREAL *pvalue)
This function decodes the contents of a float or double data type.
- int **rtXmlpDecDoubleExt** (OSCTXT *pctxt, OSUINT8 flags, OSREAL *pvalue)
This function decodes the contents of a float or double data type.
- int **rtXmlpDecDynBase64Str** (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a Base64-encode binary string.
- int **rtXmlpDecDynBitString** (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a bit string value.

- int **rtXmlpDecDynHexStr** (OSCTXT *pctxt, OSDynOctStr *pvalue)
This function decodes a contents of a hexBinary string.
- int **rtXmlpDecDynUnicodeStr** (OSCTXT *pctxt, const OSUNICHAR **ppdata, OSSIZE *pnchars)
This function decodes a Unicode string data type.
- int **rtXmlpDecDynUTF8Str** (OSCTXT *pctxt, const OSUTF8CHAR **outdata)
This function decodes the contents of a UTF-8 string data type.
- int **rtXmlpDecUTF8Str** (OSCTXT *pctxt, OSUTF8CHAR *out, OSSIZE max_len)
This function decodes the contents of a UTF-8 string data type.
- int **rtXmlpDecGDay** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gDay' type.
- int **rtXmlpDecGMonth** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonth' type.
- int **rtXmlpDecGMonthDay** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gMonthDay' type.
- int **rtXmlpDecGYear** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYear' type.
- int **rtXmlpDecGYearMonth** (OSCTXT *pctxt, OSXSDDateTime *pvalue)
This function decodes a variable of the XSD 'gYearMonth' type.
- int **rtXmlpDecHexStr** (OSCTXT *pctxt, OSOCTET *pvalue, OSUINT32 *pnocts, OSINT32 bufsize)
This function decodes the contents of a hexBinary string into a static memory structure.
- int **rtXmlpDecInt** (OSCTXT *pctxt, OSINT32 *pvalue)
This function decodes the contents of a 32-bit integer data type.
- int **rtXmlpDecInt8** (OSCTXT *pctxt, OSINT8 *pvalue)
This function decodes the contents of an 8-bit integer data type (i.e.
- int **rtXmlpDecInt16** (OSCTXT *pctxt, OSINT16 *pvalue)
This function decodes the contents of a 16-bit integer data type.
- int **rtXmlpDecInt64** (OSCTXT *pctxt, OSINT64 *pvalue)
This function decodes the contents of a 64-bit integer data type.
- int **rtXmlpDecNamedBits** (OSCTXT *pctxt, const OSBitMapItem *pBitMap, OSOCTET *pvalue, OSUINT32 *pnbits, OSUINT32 bufsize)
This function decodes the contents of a named bit field.
- int **rtXmlpDecStrList** (OSCTXT *pctxt, OSRTDList *plist)
This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.
- int **rtXmlpDecTime** (OSCTXT *pctxt, OSXSDDateTime *pvalue)

This function decodes a variable of the XSD 'time' type.

- int **rtXmlpDecUInt** (OSCTXT *pctxt, OSUINT32 *pvalue)

This function decodes the contents of an unsigned 32-bit integer data type.

- int **rtXmlpDecUInt8** (OSCTXT *pctxt, OSOCTET *pvalue)

This function decodes the contents of an unsigned 8-bit integer data type (i.e.

- int **rtXmlpDecUInt16** (OSCTXT *pctxt, OSUINT16 *pvalue)

This function decodes the contents of an unsigned 16-bit integer data type.

- int **rtXmlpDecUInt64** (OSCTXT *pctxt, OSUINT64 *pvalue)

This function decodes the contents of an unsigned 64-bit integer data type.

- int **rtXmlpDecXmlStr** (OSCTXT *pctxt, OSXMLSTRING *outdata)

This function decodes the contents of an XML string data type.

- int **rtXmlpDecXmlStrList** (OSCTXT *pctxt, OSRTDList *plist)

This function decodes a list of space-separated tokens and returns each token as a separate item on the given list.

- int **rtXmlpDecXSIAttr** (OSCTXT *pctxt, const OSXMLNameFragments *attrName)

This function decodes XSI (XML Schema Instance) attributes that may be present in any arbitrary XML element within a document.

- int **rtXmlpDecXSITypeAttr** (OSCTXT *pctxt, const OSXMLNameFragments *attrName, const OS-UTF8CHAR **ppAttrValue)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).

- int **rtXmlpGetAttributeID** (const OSXMLStrFragment *attrName, OSINT16 nsidx, OSSIZE nAttr, const OS-XMLAttrDescr attrNames[], OSUINT32 attrPresent[])

This function finds an attribute in the descriptor table.

- int **rtXmlpGetNextElem** (OSCTXT *pctxt, OSXMLElemDescr *pElem, OSINT32 level)

This function parse the next element start tag.

- int **rtXmlpGetNextElemID** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nrows, OSINT32 level, OSBOOL continueParse)

This function parses the next start tag and finds the index of the element name in the descriptor table.

- int **rtXmlpMarkLastEventActive** (OSCTXT *pctxt)

This function marks current tag as unprocessed.

- int **rtXmlpMatchStartTag** (OSCTXT *pctxt, const OSUTF8CHAR *elemLocalName, OSINT16 nsidx)

This function parses the next start tag that matches with given name.

- int **rtXmlpMatchEndTag** (OSCTXT *pctxt, OSINT32 level)

This function parse next end tag that matches with given name.

- OSBOOL **rtXmlpHasAttributes** (OSCTXT *pctxt)

This function checks accessibility of attributes.

- int **rtXmlpGetAttributeCount** (OSCTXT *pctxt)

This function returns number of attributes in last processed start tag.
- int **rtXmlpSelectAttribute** (OSCTXT *pctxt, OSXMLNameFragments *pAttr, OSINT16 *nsidx, OSSIZE attrIndex)

This function selects attribute to decode.
- OSINT32 **rtXmlpGetCurrentLevel** (OSCTXT *pctxt)

This function returns current nesting level.
- void **rtXmlpSetWhiteSpaceMode** (OSCTXT *pctxt, **OSXMLWhiteSpaceMode** whiteSpaceMode)

Sets the whitespace treatment mode.
- OSBOOL **rtXmlpSetMixedContentMode** (OSCTXT *pctxt, OSBOOL mixedContentMode)

Sets mixed content mode.
- void **rtXmlpSetListMode** (OSCTXT *pctxt)

Sets list mode.
- OSBOOL **rtXmlpListHasItem** (OSCTXT *pctxt)

Check for end of decoded token list.
- void **rtXmlpCountListItems** (OSCTXT *pctxt, OSSIZE *itemCnt)

Count tokens in list.
- int **rtXmlpGetNextSeqElemID2** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, const **OSXMLGroupDesc** *pGroup, int groups, int curID, int lastMandatoryID, OSBOOL groupMode, OSBOOL checkRepeat)

This function parses the next start tag and finds index of element name in descriptor table.
- int **rtXmlpGetNextSeqElemID** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, const **OSXMLGroupDesc** *pGroup, int curID, int lastMandatoryID, OSBOOL groupMode)

This function parses the next start tag and finds index of element name in descriptor table.
- int **rtXmlpGetNextSeqElemIDExt** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, const **OSXMLGroupDesc** *ppGroup, const OSBOOL *extRequired, int postExtRootID, int curID, int lastMandatoryID, OSBOOL groupMode)

This is an ASN.1 extension-supporting version of rtXmlpGetNextSeqElemID.
- int **rtXmlpGetNextAllElemID** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nRows, const OSUINT8 *pOrder, OSSIZE nOrder, OSSIZE maxOrder, int anyID)

This function parses the next start tag and finds index of element name in descriptor table.
- int **rtXmlpGetNextAllElemID16** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nRows, const OSUINT16 *pOrder, OSSIZE nOrder, OSSIZE maxOrder, int anyID)

This function parses the next start tag and finds index of element name in descriptor table.
- int **rtXmlpGetNextAllElemID32** (OSCTXT *pctxt, const OSXMLElemIDRec *tab, OSSIZE nRows, const OSUINT32 *pOrder, OSSIZE nOrder, OSSIZE maxOrder, int anyID)

This function parses the next start tag and finds index of element name in descriptor table.

- void **rtXmlpSetNamespaceTable** (OSCTXT *pctxt, const OSUTF8CHAR *namespaceTable[], OSSIZE nmNamespaces)

Sets user namespace table.
- int **rtXmlpCreateReader** (OSCTXT *pctxt)

Creates pull parser reader structure within the context.
- void **rtXmlpHideAttributes** (OSCTXT *pctxt)

Disable access to attributes.
- OSBOOL **rtXmlpNeedDecodeAttributes** (OSCTXT *pctxt)

This function checks if attributes were previously decoded.
- void **rtXmlpMarkPos** (OSCTXT *pctxt)

Save current decode position.
- void **rtXmlpRewindToMarkedPos** (OSCTXT *pctxt)

Rewind to saved decode position.
- void **rtXmlpResetMarkedPos** (OSCTXT *pctxt)

Reset saved decode position.
- int **rtXmlpGetXSITypeAttr** (OSCTXT *pctxt, const OSUTF8CHAR **ppAttrValue, OSINT16 *nsidx, OSSIZE *pLocalOffs)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type).
- int **rtXmlpGetXmlnsAttrs** (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function decodes namespace attributes from start tag and adds them to the given list.
- int **rtXmlpDecXSIAttrs** (OSCTXT *pctxt)

This function decodes XSI (XML Schema Instance) that may be present in any arbitrary XML element within a document.
- OSBOOL **rtXmlpIsEmptyElement** (OSCTXT *pctxt)

Check element content: empty or not.
- int **rtXmlEncAttrC14N** (OSCTXT *pctxt)

This function used only in C14 mode.
- struct OSXMLReader * **rtXmlpGetReader** (OSCTXT *pctxt)

This function fetches the XML reader structure from the context for use in low-level pull parser calls.
- OSBOOL **rtXmlpIsLastEventDone** (OSCTXT *pctxt)

Check processing status of current tag.
- int **rtXmlpGetXSITypeIndex** (OSCTXT *pctxt, const OSXMLItemDescr typetab[], OSSIZE typetabsiz)

This function decodes the contents of an XSI (XML Schema Instance) type attribute (xsi:type) and find type index in descriptor table.
- int **rtXmlpLookupXSITypeIndex** (OSCTXT *pctxt, const OSUTF8CHAR *pXsiType, OSINT16 xsiTypeIdx, const OSXMLItemDescr typetab[], OSSIZE typetabsiz)

This function find index of XSI (XML Schema Instance) type in descriptor table.

- void [rtXmlpForceDecodeAsGroup](#) (OSCTXT *pctxt)
Disable skipping of unknown elements in optional sequence tail.
- OSBOOL [rtXmlpIsDecodeAsGroup](#) (OSCTXT *pctxt)
This function checks if "decode as group" mode was forced.
- OSBOOL [rtXmlpIsUTF8Encoding](#) (OSCTXT *pctxt)
This function checks if the encoding specified in XML header is UTF-8.
- int [rtXmlpReadBytes](#) (OSCTXT *pctxt, OSOCTET *pbuf, OSSIZE nbytes)
This function reads the specified number of bytes directly from the underlying XML parser stream.

8.2.1 Detailed Description

XML low-level C encode/decode functions.

Definition in file [osrtxml.h](#).

8.2.2 Typedef Documentation

8.2.2.1 **typedef struct OSXMLGroupDesc OSXMLGroupDesc**

[OSXMLGroupDesc](#) describes how entries in an OSXMЛЕlemIDRec array make up a group.

Here, "group" means a set of elements, any of which may be matched next. This does not correspond directly to an XSD group.

For example, if elementA is optional and followed by non-optional elementB, then there will be a group that contains both elements. There will also be a group that contains only elementB; this will be the group of interest after elementA is matched.

8.2.3 Function Documentation

8.2.3.1 **const OSUTF8CHAR* rtSaxGetAttrValue (const OSUTF8CHAR * attrName, const OSUTF8CHAR *const * attrs)**

This function looks up an attribute in the attribute array returned by SAX to the startElement function.

Parameters

attrName Name of the attribute to find.

attrs Attribute array returned in SAX startElement function. This is an array of character strings containing name1, value1, name2, value2, ... List is terminated by a null name.

Returns

Pointer to character string containing attribute value or NULL if attrName not found.

8.2.3.2 OSINT16 rtSaxGetElemID (OSINT16 **pState*, OSINT16 *prevElemIdx*, const OSUTF8CHAR * *localName*, OSINT32 *nsidx*, const OSSAXElemTableRec *idtab*[], const OSINT16 **fstab*, OSINT16 *fstabRows*, OSINT16 *fstabCols*)

This function looks up a sequence element name in the given element info array.

If ensures elements are received in the correct order and also sets the required element count variable.

Parameters

pState The pointer to state variable to be changed.

prevElemIdx Previous index of element. The search will be started from this element for better performance.

localName Local name of XML element

nsidx Namespace index

idtab Element ID table

fstab Finite state table

fstabRows Number of rows in *fstab*.

fstabCols Number of columns in *fstab*.

8.2.3.3 OSINT16 rtSaxGetElemID8 (OSINT16 **pState*, OSINT16 *prevElemIdx*, const OSUTF8CHAR * *localName*, OSINT32 *nsidx*, const OSSAXElemTableRec *idtab*[], const OSINT8 **fstab*, OSINT16 *fstabRows*, OSINT16 *fstabCols*)

This function is a space optimized version of *rtSaxGetElemID*.

It operates with array of 8-bit integers (OSINT8) instead of 32-bit integers (int).

Parameters

pState The pointer to state variable to be changed.

prevElemIdx Previous index of element. The search will be started from this element + 1 for better performance.

localName Local name of XML element

nsidx Namespace index

idtab Element ID table

fstab Finite state table (array of 8-bit integers)

fstabRows Number of rows in *fstab*.

fstabCols Number of columns in *fstab*.

8.2.3.4 OSBOOL rtSaxHasXMLNSAttrs (const OSUTF8CHAR *const **attrs*)

This function checks if the given attribute list contains one or more XML namespace attributes (xmlns).

Parameters

attrs Attribute list in form passed by parser into SAX startElement function.

Returns

TRUE, if xmlns attribute found in list.

8.2.3.5 OSBOOL rtSaxIsEmptyBuffer (OSCTXT * *pctxt*)

This function checks if the buffer in the context is empty or not.

Parameters

pctxt Pointer to OSCTXT structure

Returns

TRUE, if the buffer contains empty string.

8.2.3.6 int rtSaxSortAttrs (OSCTXT * *pctxt*, const OSUTF8CHAR *const * *attrs*, OSUINT16 ** *order*)

This function sorts a SAX attribute list in ascending order based on attribute name.

It currently only supports unqualified attributes.

Parameters

pctxt Pointer to OSCTXT structure.

attrs Standard SAX attribute list. Entry i is attribute name and i+1 is value. List is terminated by a null name.

order Order array containing the order of sorted attributes. This array is allocated using rtxMemAlloc, it can be freed using rtxMemFreePtr or will be freed when the context is freed. The list holds indicies to name items in the attribute list that is passed in.

Returns

If success, positive value contains number of attributes in attrs; if failure, negative status code.

8.2.3.7 int rtSaxStrListMatch (OSCTXT * *pctxt*)

This function matches the list of strings.

It is used for matching NMOKENS, IDREFS, NMENTITIES.

Parameters

pctxt Pointer to OSCTXT structure

Returns

0 - if success, negative value is error.

8.2.3.8 int rtSaxStrListParse (OSCTXT * *pctxt*, OSRTMEMBUF * *pMemBuf*, OSRTDList * *pvalue*)

This function parses the list of strings.

It is used for parsing NMOKENS, IDREFS, NMENTITIES.

Parameters

pctxt Pointer to OSCTXT structure. Can be NULL, if pMemBuf is not NULL.

pMemBuf Pointer to memory buffer structure. Can be NULL, if pctxt is not NULL.

pvalue Doubly-linked list for parsed strings.

Returns

0 - if success, negative value is error.

8.2.3.9 OSBOOL rtXmlCmpBase64Str (OSUINT32 *nocts1*, const OSOCTET * *data1*, const OSUTF8CHAR * *data2*)

This function compares an array of octets to a base64 string.

Parameters

nocts1 Number of octets in data1.

data1 Pointer to array of OSOCTET.

data2 Pointer to null-terminated array of OSUTF8CHAR.

Returns

TRUE if data2 is a base64 string representation of data1, false otherwise.

8.2.3.10 OSBOOL rtXmlCmpHexStr (OSUINT32 *nocts1*, const OSOCTET * *data1*, const OSUTF8CHAR * *data2*)

This function compares an array of octets to a hex string.

Parameters

nocts1 Number of octets in data1.

data1 Pointer to array of OSOCTET.

data2 Pointer to null-terminated array of OSUTF8CHAR.

Returns

TRUE if data2 is a hex string representation of data1, false otherwise.

8.2.3.11 int rtXmlCreateFileInputSource (OSCTXT * *pctxt*, const char * *filepath*)

This function creates an XML document file input source.

The document can then be decoded by invoking an XML decode function.

Parameters

pctxt Pointer to context block structure.

filepath Full pathname of XML document file to open.

Returns

Completion status of operation:

- 0 = success,
- negative return value is error.

8.2.3.12 int rtXmlInitContext (OSCTXT * *pctxt*)

This function initializes a context variable for XML encoding or decoding.

Parameters

pctxt Pointer to OSCTXT structure

8.2.3.13 int rtXmlInitContextUsingKey (OSCTXT * *pctxt*, const OSOCTET * *key*, OSSIZE *keylen*)

This function initializes a context using a run-time key.

This form is required for evaluation and limited distribution software. The compiler will generate a macro for rtXmlInitContext in the rtkey.h file that will invoke this function with the generated run-time key.

Parameters

pctxt The pointer to the context structure variable to be initialized.

key Key data generated by ASN1C compiler.

keylen Key data field length.

Returns

Completion status of operation:

- 0 (ASN_OK) = success,
- negative return value is error.

8.2.3.14 int rtXmlInitCtxtAppInfo (OSCTXT * *pctxt*)

This function initializes the XML application info section of the given context.

Parameters

pctxt Pointer to OSCTXT structure

8.2.3.15 int rtXmlMatchBase64Str (OSCTXT * *pctxt*, OSSIZE *minLength*, OSSIZE *maxLength*)

This function tests the context buffer for containing a correct base64 string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

minLength A minimal length of expected string.

maxLength A maximal length of expected string.

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.16 int rtXmlMatchDate (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct date string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.17 int rtXmlMatchDateTime (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct dateTime string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.18 int rtXmlMatchGDay (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gDay string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.19 int rtXmlMatchGMonth (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gMonth string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.20 int rtXmlMatchGMonthDay (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gMonthDay string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.21 int rtXmlMatchGYear (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gYear string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.22 int rtXmlMatchGYearMonth (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct gYearMonth string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.23 int rtXmlMatchHexStr (OSCTXT * *pctxt*, OSSIZE *minLength*, OSSIZE *maxLength*)

This function tests the context buffer for containing a correct hexadecimal string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

minLength A minimal length of expected string.

maxLength A maximal length of expected string.

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.24 int rtXmlMatchTime (OSCTXT * *pctxt*)

This function tests the context buffer for containing a correct time string.

It does not decode the value.

Parameters

pctxt Pointer to OSCTXT structure

Returns

If the string in the context buffer is a correct one, function returns zero. Error code (negative) will be returned otherwise. Note, error record will NOT be added in the error's list of the context.

8.2.3.25 void rtXmlMemFreeAnyAttrs (OSCTXT * *pctxt*, OSRTDList * *pAnyAttrList*)

This function frees a list of anyAttribute that is a member of OSXSDAnyType structure.

Parameters

pctxt Pointer to context block structure.

pAnyAttrList Pointer to list of anyAttribute that is to be freed.

8.2.3.26 OSUTF8CHAR* rtXmlNewQName (OSCTXT * *pctxt*, const OSUTF8CHAR * *localName*, const OSUTF8CHAR * *prefix*)

This function creates a new QName given the localName and prefix parts.

Parameters

pctxt Pointer to a context structure.

localName Element local name.

prefix Namespace prefix.

Returns

QName value. Memory for the value will have been allocated by rtxMemAlloc and thus must be freed using one of the rtxMemFree functions. The value will be NULL if no dynamic memory was available.

8.2.3.27 int rtXmlPrepareContext (OSCTXT **pctxt*)

This function prepares the context for another encode by setting the state back to OSXMLINIT and moving the buffer's cursor back to the beginning of the buffer.

Parameters

pctxt Pointer to OSCTXT structure

Returns

0 if OK, negative status code if error.

8.2.3.28 int rtXmlSetEncC14N (OSCTXT **pctxt*, OSBOOL *value*)

This function sets the option to encode in C14N mode.

Parameters

pctxt Pointer to OSCTXT structure

value Boolean value: true = C14N mode enabled.

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.29 int rtXmlSetEncDocHdr (OSCTXT **pctxt*, OSBOOL *value*)

This function sets the option to add the XML document header (i.e.

<?xml version="1.0" encoding="UTF-8"?>) to the XML output stream.

Parameters

pctxt Pointer to OSCTXT structure

value Boolean value: true = add document header

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.30 int rtXmlSetEncodingStr (OSCTXT **pctxt*, const OSUTF8CHAR **encodingStr*)

This function sets the XML output encoding to the given value.

Currently, UTF-8/UTF-16/ISO-8859-1 encodings are supported.

Parameters

pctxt Pointer to OSCTXT structure

encodingStr XML output encoding format

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.31 int rtXmlSetEncXSINamespace (OSCTXT **pctxt*, OSBOOL *value*)

This function sets a flag in the context that indicates the XSI namespace declaration (xmlns:xsi) should be added to the encoded XML instance.

Parameters

pctxt Pointer to OSCTXT structure
value Boolean value: true = encode XSI namespace attribute.

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.32 int rtXmlSetEncXSINilAttr (OSCTXT **pctxt*, OSBOOL *value*)

This function sets a flag in the context that indicates the XSI attribute declaration (xmlns:xsi) should be added to the encoded XML instance.

Parameters

pctxt Pointer to OSCTXT structure
value Boolean value: true = encode xsi:nil attribute.

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.33 int rtXmlSetFormatting (OSCTXT **pctxt*, OSBOOL *doFormatting*)

This function sets XML output formatting to the given value.

If TRUE (the default), the XML document is formatted with indentation and newlines. If FALSE, all whitespace between elements is suppressed. Turning formatting off can provide more compressed documents and also a more canonical representation which is important for security applications. Also the function 'rtXmlSetIndent' might be used to set the exact size of indentation.

Parameters

pctxt Pointer to OSCTXT structure
doFormatting Boolean value indicating if formatting is to be done

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.34 int rtXmlSetIndent (OSCTXT **pctxt*, OSUINT8 *indent*)

This function sets XML output indent to the given value.

Parameters

pctxt Pointer to OSCTXT structure

indent Number of spaces per indent. Default is 3.

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.35 int rtXmlSetIndentChar (OSCTXT * *pctxt*, char *indentChar*)

This function sets XML output indent character to the given value.

Parameters

pctxt Pointer to OSCTXT structure

indentChar Indent character. Default is space.

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.36 void rtXmlSetNamespacesSet (OSCTXT * *pctxt*, OSBOOL *value*)

This function sets the context 'namespaces are set' flag.

This indicates that namespace declarations have been set either by the decoder or externally by the end user. It is used by the encoder to know not to set the default namespaces specified in the schema before starting encoding.

Parameters

pctxt Pointer to OSCTXT structure.

value Boolean value to which flag is to be set.

8.2.3.37 int rtXmlSetNoNSSchemaLocation (OSCTXT * *pctxt*, const OSUTF8CHAR * *schemaLocation*)

This function sets the XML Schema Instance (xsi) no namespace schema location attribute to be added to an encoded document.

This attribute is optional: if not set, no xsi:noNamespaceSchemaLocation attribute will be added.

Parameters

pctxt Pointer to OSCTXT structure

schemaLocation Schema location attribute value

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.38 int rtXmlSetNSPrefixLinks (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function sets namespace prefix/URI links in the namespace prefix stack in the context structure.

Parameters

pctxt Pointer to OSCTXT structure.

pNSAttrs List of namespace attributes.

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.39 int rtXmlSetSchemaLocation (OSCTXT * *pctxt*, const OSUTF8CHAR * *schemaLocation*)

This function sets the XML Schema Instance (xsi) schema location attribute to be added to an encoded document.

This attribute is optional: if not set, no xsi:schemaLocation attribute will be added.

Parameters

pctxt Pointer to OSCTXT structure

schemaLocation Schema location attribute value

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.40 void rtXmlSetSoapVersion (OSCTXT * *pctxt*, OSUINT8 *version*)

This function sets the SOAP version number.

Parameters

pctxt Pointer to OSCTXT structure

version SOAP version number as 2 digit integer (for example, 11 is SOAP version 1.1, 12 is version 1.2, etc.)

8.2.3.41 int rtXmlSetWriteBOM (OSCTXT * *pctxt*, OSBOOL *write*)

This function sets whether the Unicode byte order mark is encoded.

Parameters

pctxt Pointer to OSCTXT structure

write TRUE to encode BOM, FALSE to not encode BOM.

Returns

Status of operation: 0 if OK, negative status code if error.

8.2.3.42 int rtXmlSetXSITypeAttr (OSCTXT * *pctxt*, const OSUTF8CHAR * *xsiType*)

This function sets the XML Schema Instance (xsi) type attribute value.

This will cause an xsi:type attribute to be added to the top level element in an encoded XML instance.

Parameters

pctxt Pointer to OSCTXT structure

xsiType xsi:type attribute value

Returns

Status of operation: 0 if OK, negative status code if error.

8.3 rtXmlErrCodes.h File Reference

List of numeric status codes that can be returned by ASN1C run-time functions and generated code.

```
#include "rtxsrc/rtxErrCodes.h"
```

Defines

- #define **XML_OK_EOB** 0xffffffff
End of block marker.
- #define **XML_OK_FRAG** XML_OK_EOB
Maintained for backward compatibility.
- #define **XML_E_BASE** -200
Error base.
- #define **XML_E_GENERR** (XML_E_BASE)
General error.
- #define **XML_E_INVSYMBOL** (XML_E_BASE-1)
An invalid XML symbol (character) was detected at the given point in the parse stream.
- #define **XML_E_TAGMISMATCH** (XML_E_BASE-2)
Start/end tag mismatch.
- #define **XML_E_DUPLATTR** (XML_E_BASE-3)
Duplicate attribute found.
- #define **XML_E_BADCHARREF** (XML_E_BASE-4)
Bad character reference found.
- #define **XML_E_INVMODE** (XML_E_BASE-5)
Invalid mode.
- #define **XML_E_UNEXPEOF** (XML_E_BASE-6)
Unexpected end of file (document).
- #define **XML_E_NOMATCH** (XML_E_BASE-7)
Current tag is not matched to specified one.
- #define **XML_E_ELEMMISRQ** (XML_E_BASE-8)
Missing required element.
- #define **XML_E_ELEMSMISRQ** (XML_E_BASE-9)
Missing required elements.
- #define **XML_E_TOOWEWELEMS** (XML_E_BASE-10)
The number of elements in a repeating collection was less than the number of elements specified in the XSD minOccurs facet for this type or element.

- #define **XML_E_UNEXPSTARTTAG** (XML_E_BASE-11)
Unexpected start tag.
- #define **XML_E_UNEXPENDTAG** (XML_E_BASE-12)
Unexpected end tag.
- #define **XML_E_IDNOTFOU** (XML_E_BASE-13)
Expected identifier not found.
- #define **XML_E_INVTYPEINFO** (XML_E_BASE-14)
Unknown xsi:type.
- #define **XML_E_NSURINOTFOU** (XML_E_BASE-15)
Namespace URI not defined for given prefix.
- #define **XML_E_KEYNOTFOU** (XML_E_BASE-16)
Keyref constraint has some key that not present in refered constraint.
- #define **XML_E_DUPLKEY** (XML_E_BASE-17)
Key or unique constraint has duplicated key.
- #define **XML_E_FLDABSENT** (XML_E_BASE-18)
Some key has no full set of fields.
- #define **XML_E_DUPLFLD** (XML_E_BASE-19)
Some key has more than one value for field.
- #define **XML_E_NOTEEMPTY** (XML_E_BASE-20)
An element was not empty when expected.

8.3.1 Detailed Description

List of numeric status codes that can be returned by ASN1C run-time functions and generated code.

Definition in file [rtXmlErrCodes.h](#).

8.4 rtXmlExternDefs.h File Reference

XML external definitions macro.

8.4.1 Detailed Description

XML external definitions macro. This is used for Windows to properly declare function scope within DLL's.

Definition in file [rtXmlExternDefs.h](#).

8.5 rtXmlKeyArray.h File Reference

- Implementation of a dynamic pointer sorted array.

```
#include "rtxsrc/rtxContext.h"
#include "rtxmlsrc/rtXmlExternDefs.h"
```

Functions

- int [rtXmlKeyArrayInit](#) (OSCTXT *pctxt, OSXSDKeyArray *pArray, OSUINT32 nmFields, OSBOOL key, const char *name)
Initialize the array by allocating memory for it.
- void [rtXmlKeyArraySetString](#) (OSXSDKeyArray *pArray, const OSUTF8CHAR *pValue, OSUINT32 fldNum)
Set the given field's value to the given string value.
- void [rtXmlKeyArraySetInt](#) (OSXSDKeyArray *pArray, OSINT32 value, OSUINT32 fldNum)
Set the given field's value to the given integer value.
- void [rtXmlKeyArraySetUInt](#) (OSXSDKeyArray *pArray, OSUINT32 value, OSUINT32 fldNum)
Set the given field's value to the given unsigned integer value.
- void [rtXmlKeyArraySetDecimal](#) (OSXSDKeyArray *pArray, const OSREAL *value, OSUINT32 fldNum)
Set the given field's value to the given decimal value.
- int [rtXmlKeyArrayAdd](#) (OSCTXT *pctxt, OSXSDKeyArray *pArray)
Once all the fields for a key are set, invoke this method to add the key.
- int [rtXmlKeyArrayContains](#) (OSCTXT *pctxt, OSXSDKeyArray *pArray)
Once all the fields for a key are set, this method is used to check whether the key is already present in the array of keys.

8.5.1 Detailed Description

- Implementation of a dynamic pointer sorted array.

Definition in file [rtXmlKeyArray.h](#).

8.5.2 Function Documentation

8.5.2.1 int [rtXmlKeyArrayAdd](#) (OSCTXT *pctxt, OSXSDKeyArray *pArray)

Once all the fields for a key are set, invoke this method to add the key.

It will report an error if any of the following are true:

- a field was skipped and the constraint is a key constraint
- a field was set more than once This method adds the "new" key (pointed to by pArray) into the correct place within the array of keys (and their fields), also pointed to by pArray.

8.5.2.2 int rtXmlKeyArrayContains (OSCTXT * *pctxt*, OSXSDKeyArray * *pArray*)

Once all the fields for a key are set, this method is used to check whether the key is already present in the array of keys.

Thus, to check a key ref, you set all the fields, then invoke this method. You do NOT invoke rtXmlKeyArrayAdd.

Returns

0 if key is found as expected

8.5.2.3 int rtXmlKeyArrayInit (OSCTXT * *pctxt*, OSXSDKeyArray * *pArray*, OSUINT32 *nmFields*, OSBOOL *key*, const char * *name*)

Initialize the array by allocating memory for it.

Parameters

pctxt

pArray The array whose data should be initialized.

nmFields The number of fields in the key whose data will be held in pArray->data.

key TRUE if the data is for a key; FALSE if for a unique identity constraint.

name of the identity constraint

8.5.2.4 void rtXmlKeyArraySetDecimal (OSXSDKeyArray * *pArray*, const OSREAL * *value*, OSUINT32 *fldNum*)

Set the given field's value to the given decimal value.

see comment on set* methods above.

8.5.2.5 void rtXmlKeyArraySetInt (OSXSDKeyArray * *pArray*, OSINT32 *value*, OSUINT32 *fldNum*)

Set the given field's value to the given integer value.

see comment on set* methods above.

8.5.2.6 void rtXmlKeyArraySetString (OSXSDKeyArray * *pArray*, const OSUTF8CHAR * *pValue*, OSUINT32 *fldNum*)

Set the given field's value to the given string value.

see comment on set* methods above.

8.5.2.7 void rtXmlKeyArraySetUInt (OSXSDKeyArray * *pArray*, OSUINT32 *value*, OSUINT32 *fldNum*)

Set the given field's value to the given unsigned integer value.

see comment on set* methods above.

8.6 rtXmlNamespace.h File Reference

XML namespace handling structures and function definitions.

```
#include "rtxsrc/rtxContext.h"
#include "rtxsrc/rtxDynPtrArray.h"
#include "rtxsrc/rtxXmlQName.h"
#include "rtxmlsrc/rtXmlExternDefs.h"
```

Defines

- #define **RTXMLNSSETQNAME**(qname, pNS)

This macro populates the given QName structure with information from the given namespace structure (namespace URI and prefix).

Functions

- OSXMLNamespace * **rtXmlNSAddNamespace** (OSCTXT *pctxt, OSRTDList *pNSAttrs, const OS-UTF8CHAR *prefix, const OSUTF8CHAR *uri)

This function adds a namespace to the context namespace list.
- OSBOOL **rtXmlNSEqual** (OSXMLNamespace *pNS1, OSXMLNamespace *pNS2)

This function checks if two namespace records are equal.
- void **rtXmlNSFreeAttrList** (OSCTXT *pctxt, OSRTDList *pNSAttrs)

This function frees dynamic memory used to hold namespace attribute values.
- const OSUTF8CHAR * **rtXmlNSGetPrefix** (OSCTXT *pctxt, const OSUTF8CHAR *uri)

This function gets a namespace prefix assigned to the given URI.
- const OSUTF8CHAR * **rtXmlNSGetPrefixUsingIndex** (OSCTXT *pctxt, const OSUTF8CHAR *uri, OS-UINT32 idx)

This function gets a namespace prefix assigned to the given URI using the given index to select a specific prefix from the URL/prefix map.
- OSUINT32 **rtXmlNSGetPrefixCount** (OSCTXT *pctxt, const OSUTF8CHAR *uri)

This function returns the total number of prefixes currently assigned to the given URI.
- int **rtXmlNSGetPrefixIndex** (OSCTXT *pctxt, const OSUTF8CHAR *uri, const OSUTF8CHAR *prefix, OS-UINT32 *pcount)

This function gets the index of a given prefix in the internal list of prefixes maintained for a given URI in the namespace stack.
- const OSUTF8CHAR * **rtXmlNSGetQName** (OSCTXT *pctxt, OSUTF8CHAR *buf, size_t bufsiz, const OS-UTF8CHAR *uri, const OSUTF8CHAR *localName)

This function creates a QName in the given fixed-site buffer.
- EXTXMLMETHOD const OSUTF8CHAR * **rtXmlNSGetAttrPrefix** (OSCTXT *pctxt, const OSUTF8CHAR *namespaceURI, OSRTDList *pNSAttrs)

This function returns a namespace prefix for use with attributes in the given namespace.

- const OSUTF8CHAR * [rtXmlNSGetAttrQName](#) (OSCTXT *pctxt, OSUTF8CHAR *buf, size_t bufsiz, OSXMLNamespace *pNS, const OSUTF8CHAR *localName, OSRTDList *pNSAttrs)

This function creates a QName for a qualified attribute.
- OSXMLNamespace * [rtXmlNSLookupURI](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri)

This function looks up a namespace in the context namespace stack using URI as the key value.
- OSXMLNamespace * [rtXmlNSLookupURIInList](#) (OSRTDList *pNSAttrs, const OSUTF8CHAR *uri)

This function looks up a namespace in the given list using URI as the key value.
- const OSUTF8CHAR * [rtXmlNSLookupPrefixForURI](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri)

This function looks up a namespace in the context namespace stack using URI as the key value and returns a non-empty prefix, if one has been defined.
- const OSUTF8CHAR * [rtXmlNSLookupPrefix](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix)

This function looks up a namespace in the context namespace list using the prefix as the key value.
- const OSUTF8CHAR * [rtXmlNSLookupPrefixFrag](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix, size_t prefixLen)

This function looks up a namespace in the context namespace list using the prefix as the key value.
- void [rtXmlNSRemoveAll](#) (OSCTXT *pctxt)

This function removes all namespaces from the context namespace list and frees the dynamic memory used to hold the names.
- OSXMLNamespace * [rtXmlNSSetNamespace](#) (OSCTXT *pctxt, OSRTDList *pNSAttrs, const OSUTF8CHAR *prefix, const OSUTF8CHAR *uri, OSBOOL override)

This function sets a namespace in the context namespace list.
- const OSUTF8CHAR * [rtXmlNSNewPrefix](#) (OSCTXT *pctxt, const OSUTF8CHAR *uri, OSRTDList *pNSAttrs)

This function returns the next unused prefix of the form "nsX" where X is a number.
- int [rtXmlNSAddPrefixLink](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix, const OSUTF8CHAR *uri, const OSUTF8CHAR *nsTable[], OSUINT32 nsTableRowCount)

Add a prefix link at the current stack level.
- int [rtXmlNSFreeAllPrefixLinks](#) (OSCTXT *pctxt, OSXMLNSPfxLinkStackNode *pStackNavigator)

Free all prefixes links in the given namespace stack entry.
- int [rtXmlNSFreePrefixLink](#) (OSCTXT *pctxt, OSXMLNSPfxLink *plink)

Free all data within a given namespace prefix link structure.
- int [rtXmlNSGetIndex](#) (OSCTXT *pctxt, const OSUTF8CHAR *prefix)

Get namespace index for a given namespace prefix based on current namespace stack in context.
- int [rtXmlNSPush](#) (OSCTXT *pctxt)

Push new namespace prefix mapping level onto stack.

- int [rtXmlNSPop](#) (OSCTXT *pctxt)
Remove top namespace prefix mapping level from stack.
- void [rtXmlNSSetURITable](#) (OSCTXT *pctxt, const OSUTF8CHAR *data[], OSUINT32 nRows)
Set namespace URI table in context.

8.6.1 Detailed Description

XML namespace handling structures and function definitions.

Definition in file [rtXmlNamespace.h](#).

8.6.2 Define Documentation

8.6.2.1 #define RTXMLNSSETQNAME(qname, pNS)

Value:

```
if (0 != pNS) { qname.nsPrefix = pNS->prefix; qname.nsURI = pNS->uri; } \
else { qname.nsPrefix = qname.nsURI = 0; }
```

This macro populates the given QName structure with information from the given namespace structure (namespace URI and prefix).

Parameters

qname Reference to QName structure to be populated. Pointers to items in pNS are assigned directly to fields in qname. No copies of data are made.

pNS Pointer to namespace structure.

Definition at line 330 of file [rtXmlNamespace.h](#).

8.6.3 Function Documentation

8.6.3.1 OSXMLNamespace* rtXmlNSAddNamespace (OSCTXT *pctxt, OSRTDList *pNSAttrs, const OSUTF8CHAR *prefix, const OSUTF8CHAR *uri)

This function adds a namespace to the context namespace list.

Parameters

pctxt Pointer to OSCTXT structure

pNSAttrs Namespace attribute list to which namespace info is to be added.

prefix Namespace prefix to be added

uri Namespace URI to be added

Returns

Pointer to namespace structure or NULL if not added.

8.6.3.2 OSBOOL rtXmlNSEqual (OSXMLNamespace * *pNS1*, OSXMLNamespace * *pNS2*)

This function checks if two namespace records are equal.

This does a deep compare in that it will first check if the pointers are equal and then it will check if the contents are equal (same prefix and URI).

Parameters

pNS1 Pointer to first namespace records to check.

pNS2 Pointer to second record.

Returns

True if records are equal, false otherwise.

8.6.3.3 void rtXmlNSFreeAttrList (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*)

This function frees dynamic memory used to hold namespace attribute values.

Parameters

pctxt Pointer to OSCTXT structure

pNSAttrs Pointer to namespace attribute list to be freed.

8.6.3.4 EXTXMLMETHOD const OSUTF8CHAR* rtXmlNSGetAttrPrefix (OSCTXT * *pctxt*, const OSUTF8CHAR * *namespaceURI*, OSRTDList * *pNSAttrs*)

This function returns a namespace prefix for use with attributes in the given namespace.

If a prefix is not found for the namespace, a new namespace entry is created with a generated prefix.

Parameters

pctxt Pointer to OSCTXT structure

namespaceURI Pointer to namespace URI

pNSAttrs List of namespace records. If null, the namespace list in the context will be used.

Returns

The prefix.

8.6.3.5 const OSUTF8CHAR* rtXmlNSGetAttrQName (OSCTXT * *pctxt*, OSUTF8CHAR * *buf*, size_t *bufsiz*, OSXMLNamespace * *pNS*, const OSUTF8CHAR * *localName*, OSRTDList * *pNSAttrs*)

This function creates a QName for a qualified attribute.

If a prefix is not found for the name, a new namespace entry is created with a generated prefix.

Parameters

pctxt Pointer to OSCTXT structure

buf Buffer into which qname will be written.

bufsiz Size of the buffer.

pNS Pointer to namespace URI and prefix structure.

localName Local name of the item.

pNSAttrs List of namespace records. If null, the namespace list in the context will be used.

Returns

Pointer to QName buffer (buf).

8.6.3.6 const OSUTF8CHAR* rtXmlNSGetPrefix (OSCTXT **pctxt*, const OSUTF8CHAR **uri*)

This function gets a namespace prefix assigned to the given URI.

This gives preference to empty prefixes.

Parameters

pctxt Pointer to OSCTXT structure

uri Namespace URI to be searched for

Returns

Pointer to namespace prefix string. If a NULL or empty prefix was assigned to the URI, an empty string is returned. Otherwise, any assigned prefix is returned. If no prefix was assigned, null is returned.

8.6.3.7 OSUINT32 rtXmlNSGetPrefixCount (OSCTXT **pctxt*, const OSUTF8CHAR **uri*)

This function returns the total number of prefixes currently assigned to the given URI.

Parameters

pctxt Pointer to OSCTXT structure

uri Namespace URI to be searched for

Returns

Count of prefixes assigned to the URI.

8.6.3.8 int rtXmlNSGetPrefixIndex (OSCTXT **pctxt*, const OSUTF8CHAR **uri*, const OSUTF8CHAR **prefix*, OSUINT32 **pcount*)

This function gets the index of a given prefix in the internal list of prefixes maintained for a given URI in the namespace stack.

It also may return the total number of prefixes currently assigned to the URI.

Parameters

pctxt Pointer to OSCTXT structure

uri Namespace URI to be searched for

prefix Namespace prefix for which to get index.

pcount Optional pointer to an integer count variable. If provided, the total number of prefixes currently assigned to the URI will be returned.

Returns

Index to namespace prefix or -1 if the prefix is not assigned to the given URI.

8.6.3.9 const OSUTF8CHAR* rtXmlNSGetPrefixUsingIndex (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*, OSUINT32 *idx*)

This function gets a namespace prefix assigned to the given URI using the given index to select a specific prefix from the URI/prefix map.

Parameters

pctxt Pointer to OSCTXT structure

uri Namespace URI to be searched for

idx Index to prefix in map. This only has meaning when multiple prefixes have been assigned to the given URI.

Returns

Pointer to namespace prefix string

8.6.3.10 const OSUTF8CHAR* rtXmlNSGetQName (OSCTXT * *pctxt*, OSUTF8CHAR * *buf*, size_t *bufsiz*, const OSUTF8CHAR * *uri*, const OSUTF8CHAR * *localName*)

This function creates a QName in the given fixed-site buffer.

If the name will not fit in the buffer, it is truncated.

Parameters

pctxt Pointer to OSCTXT structure

buf Buffer into which qname will be written.

bufsiz Size of the buffer.

uri Namespace URI.

localName Local name of the item.

Returns

Pointer to QName buffer (buf).

8.6.3.11 const OSUTF8CHAR* rtXmlNSLookupPrefix (OSCTXT * *pctxt*, const OSUTF8CHAR * *prefix*)

This function looks up a namespace in the context namespace list using the prefix as the key value.

Parameters

pctxt Pointer to OSCTXT structure

prefix Namespace Prefix to be found.

Returns

Pointer to namespace URI or NULL if not found.

8.6.3.12 const OSUTF8CHAR* rtXmlNSLookupPrefixForURI (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*)

This function looks up a namespace in the context namespace stack using URI as the key value and returns a non-empty prefix, if one has been defined.

Parameters

pctxt Pointer to OSCTXT structure
uri Namespace URI to be found.

Returns

Pointer to non-empty prefix. NULL if URI is not found or URI has no associated non-empty prefix.

8.6.3.13 const OSUTF8CHAR* rtXmlNSLookupPrefixFrag (OSCTXT * *pctxt*, const OSUTF8CHAR * *prefix*, size_t *prefixLen*)

This function looks up a namespace in the context namespace list using the prefix as the key value.

Parameters

pctxt Pointer to OSCTXT structure
prefix Namespace Prefix to be found.
prefixLen Namespace Prefix length.

Returns

Pointer to namespace URI or NULL if not found.

8.6.3.14 OSXMLNamespace* rtXmlNSLookupURI (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*)

This function looks up a namespace in the context namespace stack using URI as the key value.

Parameters

pctxt Pointer to OSCTXT structure
uri Namespace URI to be found.

Returns

Pointer to namespace structure or NULL if not found.

8.6.3.15 OSXMLNamespace* rtXmlNSLookupURIInList (OSRTDList * *pNSAttrs*, const OSUTF8CHAR * *uri*)

This function looks up a namespace in the given list using URI as the key value.

Parameters

pNSAttrs List of namespace records.

uri Namespace URI to be found.

Returns

Pointer to namespace structure or NULL if not found.

8.6.3.16 const OSUTF8CHAR* rtXmlNSNewPrefix (OSCTXT * *pctxt*, const OSUTF8CHAR * *uri*, OSRTDList * *pNSAttrs*)

This function returns the next unused prefix of the form "nsX" where X is a number.

The new namespace declaration is added to the list provided or the context list if a NULL pointer is passed for *pNSAttrs*.

Parameters

pctxt Pointer to OSCTXT structure

uri Namespace URI. Must not be NULL or empty string.

pNSAttrs Pointer to list of namespace attributes. If null, the namespace list in the context will be used.

Returns

New namespace prefix.

8.6.3.17 void rtXmlNSRemoveAll (OSCTXT * *pctxt*)

This function removes all namespaces from the context namespace list and frees the dynamic memory used to hold the names.

Parameters

pctxt Pointer to OSCTXT structure

8.6.3.18 OSXMLNamespace* rtXmlNSSetNamespace (OSCTXT * *pctxt*, OSRTDList * *pNSAttrs*, const OSUTF8CHAR * *prefix*, const OSUTF8CHAR * *uri*, OSBOOL *override*)

This function sets a namespace in the context namespace list.

If the given namespace URI does not exist in the list, the namespace is added. If the URI is found, the action depends on the value of the override flag. If true, the value of the namespace prefix will be changed to the given prefix. If false, the existing namespace specification is not altered.

Parameters

pctxt Pointer to OSCTXT structure

pNSAttrs Namespace attribute list to which namespace info is to be added.

prefix Namespace prefix

uri Namespace URI

override Should existing definition be changed?

Returns

Pointer to namespace structure or NULL if not set.

8.7 rtXmlpCppDecFuncs.h File Reference

XML low-level C++ decode functions.

```
#include "rtxmlsrc/osrtxml.h"
#include "rtxmlsrc/OSXSDComplexType.h"
```

8.7.1 Detailed Description

XML low-level C++ decode functions. These are overloaded versions of C XML encode functions for use with C++.

Definition in file [rtXmlpCppDecFuncs.h](#).

Index

dom
 domAddAttribute, 103
 domAddCdata, 104
 domAddContent, 104
 domCreateChild, 104
 domCreateDocument, 105
 domFreeDoc, 105
 domGetAttrData, 105
 domGetChild, 105
 domGetDoc, 106
 domGetElementName, 106
 domGetNext, 106
 domGetNextAttr, 107
 domGetNodeAttributesNum, 107
 domGetNodeContent, 107
 domGetNodeFirstAttribute, 107
 domGetRootElement, 108
 domParseFile, 108
 domSaveDoc, 108
DOM API functions., 102
DOM runtime encode/decode functions., 110
 domAddAttribute
 dom, 103
 domAddCdata
 dom, 104
 domAddContent
 dom, 104
 domCreateChild
 dom, 104
 domCreateDocument
 dom, 105
 domFreeDoc
 dom, 105
 domGetAttrData
 dom, 105
 domGetChild
 dom, 105
 domGetDoc
 dom, 106
 domGetElementName
 dom, 106
 domGetNext
 dom, 106
 domGetNextAttr
 dom, 107
domGetNodeAttributesNum
 dom, 107
domGetNodeContent
 dom, 107
domGetNodeFirstAttribute
 dom, 107
domGetRootElement
 dom, 108
domParseFile
 dom, 108
domSaveDoc
 dom, 108
osrtdom.h, 117
osrtxml.h, 119
 OSXMLGroupDesc, 136
 rtSaxGetAttrValue, 136
 rtSaxGetElemID, 136
 rtSaxGetElemID8, 137
 rtSaxHasXMLNSAttrs, 137
 rtSaxIsEmptyBuffer, 137
 rtSaxSortAttrs, 138
 rtSaxStrListMatch, 138
 rtSaxStrListParse, 138
 rtXmlCmpBase64Str, 139
 rtXmlCmpHexStr, 139
 rtXmlCreateFileInputSource, 139
 rtXmlInitContext, 139
 rtXmlInitContextUsingKey, 140
 rtXmlInitCtxtAppInfo, 140
 rtXmlMatchBase64Str, 140
 rtXmlMatchDate, 140
 rtXmlMatchDateTime, 141
 rtXmlMatchGDay, 141
 rtXmlMatchGMonth, 141
 rtXmlMatchGMonthDay, 141
 rtXmlMatchGYear, 142
 rtXmlMatchGYearMonth, 142
 rtXmlMatchHexStr, 142
 rtXmlMatchTime, 143
 rtXmlMemFreeAnyAttrs, 143
 rtXmlNewQName, 143
 rtXmlPrepareContext, 143
 rtXmlSetEncC14N, 144
 rtXmlSetEncDocHdr, 144

```

rtXmlSetEncodingStr, 144
rtXmlSetEncXSINamespace, 144
rtXmlSetEncXSINilAttr, 145
rtXmlSetFormatting, 145
rtXmlSetIndent, 145
rtXmlSetIndentChar, 146
rtXmlSetNamespacesSet, 146
rtXmlSetNoNSSchemaLocation, 146
rtXmlSetNSPrefixLinks, 146
rtXmlSetSchemaLocation, 147
rtXmlSetSoapVersion, 147
rtXmlSetWriteBOM, 147
rtXmlSetXSITypeAttr, 147
OSXMLGroupDesc, 116
osrxml.h, 136

rtDom
    rtDomAddAttr, 111
    rtDomAddNode, 111
    rtDomAddNSAttrs, 111
    rtDomAddSubTree, 112
    rtDomDecodeDoc, 112
    rtDomEncAny, 113
    rtDomEncAnyAttr, 113
    rtDomEncString, 113
    rtDomEncStringValue, 114
    rtDomEncXSIAttrs, 114
    rtDomSetNode, 114
rtDomAddAttr
    rtDom, 111
rtDomAddNode
    rtDom, 111
rtDomAddNSAttrs
    rtDom, 111
rtDomAddSubTree
    rtDom, 112
rtDomDecodeDoc
    rtDom, 112
rtDomEncAny
    rtDom, 113
rtDomEncAnyAttr
    rtDom, 113
rtDomEncString
    rtDom, 113
rtDomEncStringValue
    rtDom, 114
rtDomEncXSIAttrs
    rtDom, 114
rtDomSetNode
    rtDom, 114
rtSaxGetAttrValue
    osrxml.h, 136
rtSaxGetElemID
    osrxml.h, 136
rtSaxGetElemID8
    osrxml.h, 137
rtSaxHasXMLNSAttrs
    osrxml.h, 137
rtSaxIsEmptyBuffer
    osrxml.h, 137
rtSaxSortAttrs
    osrxml.h, 138
rtSaxStrListMatch
    osrxml.h, 138
rtSaxStrListParse
    osrxml.h, 138
rtXmlCmpBase64Str
    osrxml.h, 139
rtXmlCmpHexStr
    osrxml.h, 139
rtXmlCreateFileInputSource
    osrxml.h, 139
rtXmlDec
    rtXmlDecBase64Binary, 9
    rtXmlDecBase64Str, 10
    rtXmlDecBase64StrValue, 10
    rtXmlDecBigInt, 10
    rtXmlDecBool, 11
    rtXmlDecDate, 11
    rtXmlDecDateTime, 11
    rtXmlDecDecimal, 12
    rtXmlDecDouble, 12
    rtXmlDecDynBase64Str, 12
    rtXmlDecDynHexStr, 13
    rtXmlDecDynUTF8Str, 13
    rtXmlDecEmptyElement, 13
    rtXmlDecGDay, 14
    rtXmlDecGMonth, 14
    rtXmlDecGMonthDay, 14
    rtXmlDecGYear, 15
    rtXmlDecGYearMonth, 15
    rtXmlDecHexBinary, 15
    rtXmlDecHexStr, 16
    rtXmlDecInt, 16
    rtXmlDecInt16, 17
    rtXmlDecInt64, 17
    rtXmlDecInt8, 17
    rtXmlDecNSAttr, 18
    rtXmlDecQName, 18
    rtXmlDecTime, 19
    rtXmlDecUInt, 19
    rtXmlDecUInt16, 19
    rtXmlDecUInt64, 20
    rtXmlDecUInt8, 20
    rtXmlDecUTF8Str, 20
    rtXmlDecXmlStr, 21
    rtXmlDecXSIArr, 21
    rtXmlDecXSIAtrrs, 21

```

```

rtXmlParseElementName, 22
rtXmlParseElemQName, 22
rtXmlDecBase64Binary
    rtXmlDec, 9
rtXmlDecBase64Str
    rtXmlDec, 10
rtXmlDecBase64StrValue
    rtXmlDec, 10
rtXmlDecBigInt
    rtXmlDec, 10
rtXmlDecBool
    rtXmlDec, 11
rtXmlDecDate
    rtXmlDec, 11
rtXmlDecDateTime
    rtXmlDec, 11
rtXmlDecDecimal
    rtXmlDec, 12
rtXmlDecDouble
    rtXmlDec, 12
rtXmlDecDynBase64Str
    rtXmlDec, 12
rtXmlDecDynHexStr
    rtXmlDec, 13
rtXmlDecDynUTF8Str
    rtXmlDec, 13
rtXmlDecEmptyElement
    rtXmlDec, 13
rtXmlDecGDay
    rtXmlDec, 14
rtXmlDecGMonth
    rtXmlDec, 14
rtXmlDecGMonthDay
    rtXmlDec, 14
rtXmlDecGYear
    rtXmlDec, 15
rtXmlDecGYearMonth
    rtXmlDec, 15
rtXmlDecHexBinary
    rtXmlDec, 15
rtXmlDecHexStr
    rtXmlDec, 16
rtXmlDecInt
    rtXmlDec, 16
rtXmlDecInt16
    rtXmlDec, 17
rtXmlDecInt64
    rtXmlDec, 17
rtXmlDecInt8
    rtXmlDec, 17
rtXmlDecNSAttr
    rtXmlDec, 18
rtXmlDecQName
    rtXmlDec, 18
rtXmlDecTime
    rtXmlDec, 19
rtXmlDecUInt
    rtXmlDec, 19
rtXmlDecUInt16
    rtXmlDec, 19
rtXmlDecUInt64
    rtXmlDec, 20
rtXmlDecUInt8
    rtXmlDec, 20
rtXmlDecUTF8Str
    rtXmlDec, 20
rtXmlDecXmlStr
    rtXmlDec, 21
rtXmlDecXSIAttr
    rtXmlDec, 21
rtXmlDecXSIAttrs
    rtXmlDec, 21
rtXmlEnc
    rtXmlEncAny, 30
    rtXmlEncAnyAttr, 30
    rtXmlEncAnyTypeValue, 30
    rtXmlEncBase64Binary, 31
    rtXmlEncBase64BinaryAttr, 31
    rtXmlEncBase64StrValue, 31
    rtXmlEncBigInt, 32
    rtXmlEncBigIntAttr, 32
    rtXmlEncBigIntValue, 33
    rtXmlEncBinStrValue, 33
    rtXmlEncBitString, 33
    rtXmlEncBOM, 34
    rtXmlEncBool, 34
    rtXmlEncBoolAttr, 35
    rtXmlEncBoolValue, 35
    rtXmlEncComment, 35
    rtXmlEncDate, 36
    rtXmlEncDateTime, 36
    rtXmlEncDateTimeValue, 37
    rtXmlEncDateValue, 37
    rtXmlEncDecimal, 37
    rtXmlEncDecimalAttr, 38
    rtXmlEncDecimalValue, 38
    rtXmlEncDouble, 38
    rtXmlEncDoubleAttr, 39
    rtXmlEncDoubleNormalValue, 39
    rtXmlEncDoubleValue, 40
    rtXmlEncEmptyElement, 40
    rtXmlEncEndDocument, 40
    rtXmlEncEndElement, 41
    rtXmlEncEndSoapElems, 41
    rtXmlEncEndSoapEnv, 41
    rtXmlEncFloat, 42
    rtXmlEncFloatAttr, 42
    rtXmlEncGDay, 42

```

rtXmlEncGDayValue, 43
 rtXmlEncGMonth, 43
 rtXmlEncGMonthDay, 43
 rtXmlEncGMonthDayValue, 44
 rtXmlEncGMonthValue, 44
 rtXmlEncGYear, 44
 rtXmlEncGYearMonth, 45
 rtXmlEncGYearMonthValue, 45
 rtXmlEncGYearValue, 45
 rtXmlEncHexBinary, 46
 rtXmlEncHexBinaryAttr, 46
 rtXmlEncHexStrValue, 47
 rtXmlEncIndent, 47
 rtXmlEncInt, 47
 rtXmlEncInt64, 48
 rtXmlEncInt64Attr, 48
 rtXmlEncInt64Value, 48
 rtXmlEncIntAttr, 49
 rtXmlEncIntPattern, 49
 rtXmlEncIntValue, 50
 rtXmlEncNamedBits, 50
 rtXmlEncNSAttrs, 50
 rtXmlEncReal10, 51
 rtXmlEncSoapArrayTypeAttr, 51
 rtXmlEncStartDocument, 52
 rtXmlEncStartElement, 52
 rtXmlEncStartSoapElems, 52
 rtXmlEncStartSoapEnv, 53
 rtXmlEncString, 53
 rtXmlEncStringValue, 53
 rtXmlEncStringValue2, 54
 rtXmlEncTermStartElement, 54
 rtXmlEncTime, 54
 rtXmlEncTimeValue, 55
 rtXmlEncUInt, 55
 rtXmlEncUInt64, 56
 rtXmlEncUInt64Attr, 56
 rtXmlEncUInt64Value, 56
 rtXmlEncUIntAttr, 57
 rtXmlEncUIntValue, 57
 rtXmlEncUnicodeStr, 57
 rtXmlEncUTF8Attr, 58
 rtXmlEncUTF8Attr2, 58
 rtXmlEncUTF8Str, 59
 rtXmlEncXSIAttrs, 59
 rtXmlEncXSINilAttr, 59
 rtXmlEncXSITypeAttr, 60
 rtXmlEncXSITypeAttr2, 60
 rtXmlFreeInputSource, 60
 rtXmlGetEncBufLen, 29
 rtXmlGetEncBufPtr, 29
 rtXmlGetIndent, 61
 rtXmlGetIndentChar, 61
 rtXmlGetWriteBOM, 61
 rtXmlPrintNSAttrs, 61
 rtXmlSetEncBufPtr, 62
 rtXmlEncAny
 rtXmlEnc, 30
 rtXmlEncAnyAttr
 rtXmlEnc, 30
 rtXmlEncAnyTypeValue
 rtXmlEnc, 30
 rtXmlEncAttrC14N
 rtXmlpDec, 69
 rtXmlEncBase64Binary
 rtXmlEnc, 31
 rtXmlEncBase64BinaryAttr
 rtXmlEnc, 31
 rtXmlEncBase64StrValue
 rtXmlEnc, 31
 rtXmlEncBigInt
 rtXmlEnc, 32
 rtXmlEncBigIntAttr
 rtXmlEnc, 32
 rtXmlEncBigIntValue
 rtXmlEnc, 33
 rtXmlEncBinStrValue
 rtXmlEnc, 33
 rtXmlEncBitString
 rtXmlEnc, 33
 rtXmlEncBOM
 rtXmlEnc, 34
 rtXmlEncBool
 rtXmlEnc, 34
 rtXmlEncBoolAttr
 rtXmlEnc, 35
 rtXmlEncBoolValue
 rtXmlEnc, 35
 rtXmlEncComment
 rtXmlEnc, 35
 rtXmlEncDate
 rtXmlEnc, 36
 rtXmlEncDateTime
 rtXmlEnc, 36
 rtXmlEncDateTimeValue
 rtXmlEnc, 37
 rtXmlEncDateValue
 rtXmlEnc, 37
 rtXmlEncDecimal
 rtXmlEnc, 37
 rtXmlEncDecimalAttr
 rtXmlEnc, 38
 rtXmlEncDecimalValue
 rtXmlEnc, 38
 rtXmlEncDouble
 rtXmlEnc, 38
 rtXmlEncDoubleAttr
 rtXmlEnc, 39

rtXmlEncDoubleNormalValue
 rtXmlEnc, 39
 rtXmlEncDoubleValue
 rtXmlEnc, 40
 rtXmlEncEmptyElement
 rtXmlEnc, 40
 rtXmlEncEndDocument
 rtXmlEnc, 40
 rtXmlEncEndElement
 rtXmlEnc, 41
 rtXmlEncEndSoapElems
 rtXmlEnc, 41
 rtXmlEncEndSoapEnv
 rtXmlEnc, 41
 rtXmlEncFloat
 rtXmlEnc, 42
 rtXmlEncFloatAttr
 rtXmlEnc, 42
 rtXmlEncGDay
 rtXmlEnc, 42
 rtXmlEncGDayValue
 rtXmlEnc, 43
 rtXmlEncGMonth
 rtXmlEnc, 43
 rtXmlEncGMonthDay
 rtXmlEnc, 43
 rtXmlEncGMonthDayValue
 rtXmlEnc, 44
 rtXmlEncGMonthValue
 rtXmlEnc, 44
 rtXmlEncGYear
 rtXmlEnc, 44
 rtXmlEncGYearMonth
 rtXmlEnc, 45
 rtXmlEncGYearMonthValue
 rtXmlEnc, 45
 rtXmlEncGYearValue
 rtXmlEnc, 45
 rtXmlEncHexBinary
 rtXmlEnc, 46
 rtXmlEncHexBinaryAttr
 rtXmlEnc, 46
 rtXmlEncHexStrValue
 rtXmlEnc, 47
 rtXmlEncIndent
 rtXmlEnc, 47
 rtXmlEncInt
 rtXmlEnc, 47
 rtXmlEncInt64
 rtXmlEnc, 48
 rtXmlEncInt64Attr
 rtXmlEnc, 48
 rtXmlEncInt64Value
 rtXmlEnc, 48
 rtXmlEncIntAttr
 rtXmlEnc, 49
 rtXmlEncIntPattern
 rtXmlEnc, 49
 rtXmlEncIntValue
 rtXmlEnc, 50
 rtXmlEncNamedBits
 rtXmlEnc, 50
 rtXmlEncNSAttrs
 rtXmlEnc, 50
 rtXmlEncReal10
 rtXmlEnc, 51
 rtXmlEncSoapArrayTypeAttr
 rtXmlEnc, 51
 rtXmlEncStartDocument
 rtXmlEnc, 52
 rtXmlEncStartElement
 rtXmlEnc, 52
 rtXmlEncStartSoapElems
 rtXmlEnc, 52
 rtXmlEncStartSoapEnv
 rtXmlEnc, 53
 rtXmlEncString
 rtXmlEnc, 53
 rtXmlEncStringValue
 rtXmlEnc, 53
 rtXmlEncStringValue2
 rtXmlEnc, 54
 rtXmlEncTermStartElement
 rtXmlEnc, 54
 rtXmlEncTime
 rtXmlEnc, 54
 rtXmlEncTimeValue
 rtXmlEnc, 55
 rtXmlEncUInt
 rtXmlEnc, 55
 rtXmlEncUInt64
 rtXmlEnc, 56
 rtXmlEncUInt64Attr
 rtXmlEnc, 56
 rtXmlEncUInt64Value
 rtXmlEnc, 56
 rtXmlEncUIntAttr
 rtXmlEnc, 57
 rtXmlEncUIntValue
 rtXmlEnc, 57
 rtXmlEncUnicodeStr
 rtXmlEnc, 57
 rtXmlEncUTF8Attr
 rtXmlEnc, 58
 rtXmlEncUTF8Attr2
 rtXmlEnc, 58
 rtXmlEncUTF8Str
 rtXmlEnc, 59

rtXmlEncXSIAAttrs
 rtXmlEnc, 59
 rtXmlEncXSINilAttr
 rtXmlEnc, 59
 rtXmlEncXSITypeAttr
 rtXmlEnc, 60
 rtXmlEncXSITypeAttr2
 rtXmlEnc, 60
 rtXmlErrCodes.h, 149
 rtXmlExternDefs.h, 151
 rtXmlFreeInputSource
 rtXmlEnc, 60
 rtXmlGetEncBufLen
 rtXmlEnc, 29
 rtXmlGetEncBufPtr
 rtXmlEnc, 29
 rtXmlGetIndent
 rtXmlEnc, 61
 rtXmlGetIndentChar
 rtXmlEnc, 61
 rtXmlGetWriteBOM
 rtXmlEnc, 61
 rtXmlInitContext
 osrxml.h, 139
 rtXmlInitContextUsingKey
 osrxml.h, 140
 rtXmlInitCtxtAppInfo
 osrxml.h, 140
 rtXmlKeyArray.h, 152
 rtXmlKeyArrayAdd, 152
 rtXmlKeyArrayContains, 152
 rtXmlKeyArrayInit, 153
 rtXmlKeyArraySetDecimal, 153
 rtXmlKeyArraySetInt, 153
 rtXmlKeyArraySetString, 153
 rtXmlKeyArraySetUInt, 153
 rtXmlKeyArrayAdd
 rtXmlKeyArray.h, 152
 rtXmlKeyArrayContains
 rtXmlKeyArray.h, 152
 rtXmlKeyArrayInit
 rtXmlKeyArray.h, 153
 rtXmlKeyArraySetDecimal
 rtXmlKeyArray.h, 153
 rtXmlKeyArraySetInt
 rtXmlKeyArray.h, 153
 rtXmlKeyArraySetString
 rtXmlKeyArray.h, 153
 rtXmlKeyArraySetUInt
 rtXmlKeyArray.h, 153
 rtXmlMatchBase64Str
 osrxml.h, 140
 rtXmlMatchDate
 osrxml.h, 140
 rtXmlMatchDateTime
 osrxml.h, 141
 rtXmlMatchGDay
 osrxml.h, 141
 rtXmlMatchGMonth
 osrxml.h, 141
 rtXmlMatchGMonthDay
 osrxml.h, 141
 rtXmlMatchGYear
 osrxml.h, 142
 rtXmlMatchGYearMonth
 osrxml.h, 142
 rtXmlMatchHexStr
 osrxml.h, 142
 rtXmlMatchTime
 osrxml.h, 143
 rtXmlMemFreeAnyAttrs
 osrxml.h, 143
 rtXmlNamespace.h, 154
 rtXmlNSAddNamespace, 156
 rtXmlNSEqual, 156
 rtXmlNSFreeAttrList, 157
 rtXmlNSGetAttrPrefix, 157
 rtXmlNSGetAttrQName, 157
 rtXmlNSGetPrefix, 158
 rtXmlNSGetPrefixCount, 158
 rtXmlNSGetPrefixIndex, 158
 rtXmlNSGetPrefixUsingIndex, 159
 rtXmlNSGetQName, 159
 rtXmlNSLookupPrefix, 159
 rtXmlNSLookupPrefixForURI, 159
 rtXmlNSLookupPrefixFrag, 160
 rtXmlNSLookupURI, 160
 rtXmlNSLookupURIInList, 160
 rtXmlNSNewPrefix, 161
 rtXmlNSRemoveAll, 161
 rtXmlNSSetNamespace, 161
 RTXMLNSSETQNAME, 156
 rtXmlNewQName
 osrxml.h, 143
 rtXmlNSAddNamespace
 rtXmlNamespace.h, 156
 rtXmlNSEqual
 rtXmlNamespace.h, 156
 rtXmlNSFreeAttrList
 rtXmlNamespace.h, 157
 rtXmlNSGetAttrPrefix
 rtXmlNamespace.h, 157
 rtXmlNSGetAttrQName
 rtXmlNamespace.h, 157
 rtXmlNSGetPrefix
 rtXmlNamespace.h, 158
 rtXmlNSGetPrefixCount
 rtXmlNamespace.h, 158

rtXmlNSGetPrefixIndex
 rtXmlNamespace.h, 158
 rtXmlNSGetPrefixUsingIndex
 rtXmlNamespace.h, 159
 rtXmlNSGetQName
 rtXmlNamespace.h, 159
 rtXmlNSLookupPrefix
 rtXmlNamespace.h, 159
 rtXmlNSLookupPrefixForURI
 rtXmlNamespace.h, 159
 rtXmlNSLookupPrefixFrag
 rtXmlNamespace.h, 160
 rtXmlNSLookupURI
 rtXmlNamespace.h, 160
 rtXmlNSLookupURIInList
 rtXmlNamespace.h, 160
 rtXmlNSNewPrefix
 rtXmlNamespace.h, 161
 rtXmlNSRemoveAll
 rtXmlNamespace.h, 161
 rtXmlNSSetNamespace
 rtXmlNamespace.h, 161
 RTXMLNSSETQNAME
 rtXmlNamespace.h, 156
 rtXmlParseElementName
 rtXmlDec, 22
 rtXmlParseElem QName
 rtXmlDec, 22
 rtXmlpCountListItems
 rtXmlpDec, 69
 rtXmlpCppDecFuncs.h, 162
 rtXmlpCreateReader
 rtXmlpDec, 69
 rtXmlpDec
 rtXmlEncAttrC14N, 69
 rtXmlpCountListItems, 69
 rtXmlpCreateReader, 69
 rtXmlpDecAny, 70
 rtXmlpDecAny2, 70
 rtXmlpDecAnyAttrStr, 70
 rtXmlpDecAnyElem, 71
 rtXmlpDecBase64Str, 71
 rtXmlpDecBigInt, 71
 rtXmlpDecBitString, 72
 rtXmlpDecBool, 72
 rtXmlpDecDate, 73
 rtXmlpDecDateTime, 73
 rtXmlpDecDecimal, 73
 rtXmlpDecDouble, 74
 rtXmlpDecDoubleExt, 74
 rtXmlpDecDynBase64Str, 74
 rtXmlpDecDynBitString, 75
 rtXmlpDecDynHexStr, 75
 rtXmlpDecDynUnicodeStr, 76

rtXmlpDecDynUTF8Str, 76
 rtXmlpDecGDay, 76
 rtXmlpDecGMonth, 77
 rtXmlpDecGMonthDay, 77
 rtXmlpDecGYear, 77
 rtXmlpDecGYearMonth, 78
 rtXmlpDecHexStr, 78
 rtXmlpDecInt, 79
 rtXmlpDecInt16, 79
 rtXmlpDecInt64, 79
 rtXmlpDecInt8, 80
 rtXmlpDecNamedBits, 80
 rtXmlpDecStrList, 80
 rtXmlpDecTime, 81
 rtXmlpDecUInt, 81
 rtXmlpDecUInt16, 81
 rtXmlpDecUInt64, 82
 rtXmlpDecUInt8, 82
 rtXmlpDecUTF8Str, 82
 rtXmlpDecXmlStr, 83
 rtXmlpDecXmlStrList, 83
 rtXmlpDecXSIAAttr, 84
 rtXmlpDecXSIAAttrs, 84
 rtXmlpDecXSITypeAttr, 84
 rtXmlpForceDecodeAsGroup, 85
 rtXmlpGetAttributeCount, 85
 rtXmlpGetAttributeID, 85
 rtXmlpGetCurrentLevel, 86
 rtXmlpGetNextAllElemID, 86
 rtXmlpGetNextAllElemID16, 86
 rtXmlpGetNextAllElemID32, 87
 rtXmlpGetNextElem, 87
 rtXmlpGetNextElemID, 88
 rtXmlpGetNextSeqElemID, 88
 rtXmlpGetNextSeqElemID2, 89
 rtXmlpGetNextSeqElemIDExt, 89
 rtXmlpGetReader, 90
 rtXmlpGetXmlnsAttrs, 90
 rtXmlpGetXSITypeAttr, 90
 rtXmlpGetXSITypeIndex, 91
 rtXmlpHasAttributes, 91
 rtXmlpHideAttributes, 91
 rtXmlpIsDecodeAsGroup, 92
 rtXmlpIsEmptyElement, 92
 rtXmlpIsLastEventDone, 92
 rtXmlpIsUTF8Encoding, 92
 rtXmlpListHasItem, 93
 rtXmlpLookupXSITypeIndex, 93
 rtXmlpMarkLastEventActive, 93
 rtXmlpMarkPos, 94
 rtXmlpMatchEndTag, 94
 rtXmlpMatchStartTag, 94
 rtXmlpNeedDecodeAttributes, 95
 rtXmlpReadBytes, 95

rtXmlpResetMarkedPos, 95
 rtXmlpRewindToMarkedPos, 95
 rtXmlpSelectAttribute, 96
 rtXmlpSetListMode, 96
 rtXmlpSetMixedContentMode, 96
 rtXmlpSetNamespaceTable, 96
 rtXmlpSetWhiteSpaceMode, 97
 rtXmlpDecAny
 rtXmlpDec, 70
 rtXmlpDecAny2
 rtXmlpDec, 70
 rtXmlpDecAnyAttrStr
 rtXmlpDec, 70
 rtXmlpDecAnyElem
 rtXmlpDec, 71
 rtXmlpDecBase64Str
 rtXmlpDec, 71
 rtXmlpDecBigInt
 rtXmlpDec, 71
 rtXmlpDecBitString
 rtXmlpDec, 72
 rtXmlpDecBool
 rtXmlpDec, 72
 rtXmlpDecDate
 rtXmlpDec, 73
 rtXmlpDecDateTime
 rtXmlpDec, 73
 rtXmlpDecDecimal
 rtXmlpDec, 73
 rtXmlpDecDouble
 rtXmlpDec, 74
 rtXmlpDecDoubleExt
 rtXmlpDec, 74
 rtXmlpDecDynBase64Str
 rtXmlpDec, 74
 rtXmlpDecDynBitString
 rtXmlpDec, 75
 rtXmlpDecDynHexStr
 rtXmlpDec, 75
 rtXmlpDecDynUnicodeStr
 rtXmlpDec, 76
 rtXmlpDecDynUTF8Str
 rtXmlpDec, 76
 rtXmlpDecGDay
 rtXmlpDec, 76
 rtXmlpDecGMonth
 rtXmlpDec, 77
 rtXmlpDecGMonthDay
 rtXmlpDec, 77
 rtXmlpDecGYear
 rtXmlpDec, 77
 rtXmlpDecGYearMonth
 rtXmlpDec, 78
 rtXmlpDecHexStr
 rtXmlpDec, 78
 rtXmlpDec, 78
 rtXmlpDecInt
 rtXmlpDec, 79
 rtXmlpDecInt16
 rtXmlpDec, 79
 rtXmlpDecInt64
 rtXmlpDec, 79
 rtXmlpDecInt8
 rtXmlpDec, 80
 rtXmlpDecNamedBits
 rtXmlpDec, 80
 rtXmlpDecStrList
 rtXmlpDec, 80
 rtXmlpDecTime
 rtXmlpDec, 81
 rtXmlpDecUInt
 rtXmlpDec, 81
 rtXmlpDecUInt16
 rtXmlpDec, 81
 rtXmlpDecUInt64
 rtXmlpDec, 82
 rtXmlpDecUInt8
 rtXmlpDec, 82
 rtXmlpDecUTF8Str
 rtXmlpDec, 82
 rtXmlpDecXmlStr
 rtXmlpDec, 83
 rtXmlpDecXmlStrList
 rtXmlpDec, 83
 rtXmlpDecXSIAAttr
 rtXmlpDec, 84
 rtXmlpDecXSIAAttrs
 rtXmlpDec, 84
 rtXmlpDecXSITypeAttr
 rtXmlpDec, 84
 rtXmlpForceDecodeAsGroup
 rtXmlpDec, 85
 rtXmlpGetAttributeCount
 rtXmlpDec, 85
 rtXmlpGetAttributeID
 rtXmlpDec, 85
 rtXmlpGetCurrentLevel
 rtXmlpDec, 86
 rtXmlpGetNextAllElemID
 rtXmlpDec, 86
 rtXmlpGetNextAllElemID16
 rtXmlpDec, 86
 rtXmlpGetNextAllElemID32
 rtXmlpDec, 87
 rtXmlpGetNextElem
 rtXmlpDec, 87
 rtXmlpGetNextElemID
 rtXmlpDec, 88
 rtXmlpGetNextSeqElemID
 rtXmlpDec, 88

```

    rtXmlpDec, 88
rtXmlpGetNextSeqElemID2
    rtXmlpDec, 89
rtXmlpGetNextSeqElemIDExt
    rtXmlpDec, 89
rtXmlpGetReader
    rtXmlpDec, 90
rtXmlpGetXmlNsAttrs
    rtXmlpDec, 90
rtXmlpGetXSITypeAttr
    rtXmlpDec, 90
rtXmlpGetXSITypeIndex
    rtXmlpDec, 91
rtXmlpHasAttributes
    rtXmlpDec, 91
rtXmlpHideAttributes
    rtXmlpDec, 91
rtXmlpIsDecodeAsGroup
    rtXmlpDec, 92
rtXmlpIsEmptyElement
    rtXmlpDec, 92
rtXmlpIsLastEventDone
    rtXmlpDec, 92
rtXmlpIsUTF8Encoding
    rtXmlpDec, 92
rtXmlpListHasItem
    rtXmlpDec, 93
rtXmlpLookupXSITypeIndex
    rtXmlpDec, 93
rtXmlpMarkLastEventActive
    rtXmlpDec, 93
rtXmlpMarkPos
    rtXmlpDec, 94
rtXmlpMatchEndTag
    rtXmlpDec, 94
rtXmlpMatchStartTag
    rtXmlpDec, 94
rtXmlpNeedDecodeAttributes
    rtXmlpDec, 95
rtXmlpReadBytes
    rtXmlpDec, 95
rtXmlPrepareContext
    osrxml.h, 143
rtXmlResetMarkedPos
    rtXmlpDec, 95
rtXmlRewindToMarkedPos
    rtXmlpDec, 95
rtXmlPrintNSAttrs
    rtXmlEnc, 61
rtXmlpSelectAttribute
    rtXmlpDec, 96
rtXmlpSetListMode
    rtXmlpDec, 96
rtXmlpSetMixedContentMode
    rtXmlpDec, 96
rtXmlpSetNamespaceTable
    rtXmlpDec, 96
rtXmlpSetWhiteSpaceMode
    rtXmlpDec, 97
rtXmlSetEncBufPtr
    rtXmlEnc, 62
rtXmlSetEncC14N
    osrxml.h, 144
rtXmlSetEncDocHdr
    osrxml.h, 144
rtXmlSetEncodingStr
    osrxml.h, 144
rtXmlSetEncXSINamespace
    osrxml.h, 144
rtXmlSetEncXSINilAttr
    osrxml.h, 145
rtXmlSetFormatting
    osrxml.h, 145
rtXmlSetIndent
    osrxml.h, 145
rtXmlSetIndentChar
    osrxml.h, 146
rtXmlSetNamespacesSet
    osrxml.h, 146
rtXmlSetNoNSSchemaLocation
    osrxml.h, 146
rtXmlSetNSPrefixLinks
    osrxml.h, 146
rtXmlSetSchemaLocation
    osrxml.h, 147
rtXmlSetSoapVersion
    osrxml.h, 147
rtXmlSetWriteBOM
    osrxml.h, 147
rtXmlSetXSITypeAttr
    osrxml.h, 147
rtXmlUtil
    rtXmlWriteToFile, 63
rtXmlWriteToFile
    rtXmlUtil, 63

XML decode functions., 7
XML encode functions., 23
XML pull-parser decode functions., 64
XML run-time error status codes., 98
XML utility functions., 63
XML_E_BASE
    xmlErrCodes, 99
XML_E_ELEMMISRQ
    xmlErrCodes, 99
XML_E_ELEMSMISRQ
    xmlErrCodes, 100
XML_E_FLDABSENT

```

```
    xmlErrCodes, 100
XML_E_NOMATCH
    xmlErrCodes, 100
XML_E_NSURINOTFOU
    xmlErrCodes, 100
XML_E_TAGMISMATCH
    xmlErrCodes, 100
XML_OK_EOB
    xmlErrCodes, 100
XML_OK_FRAG
    xmlErrCodes, 100
xmlErrCodes
    XML_E_BASE, 99
    XML_E_ELEMMISRQ, 99
    XML_E_ELEMSMISRQ, 100
    XML_E_FLDABSENT, 100
    XML_E_NOMATCH, 100
    XML_E_NSURINOTFOU, 100
    XML_E_TAGMISMATCH, 100
    XML_OK_EOB, 100
    XML_OK_FRAG, 100
```